

# Administrator's Configuration File Reference

*Sun™ ONE Application Server*

**Version 7**

817-2178-10  
March 2003

Copyright © 2003 Sun Microsystems, Inc., 4150 Network Circle, Santa Clara, California 95054, U.S.A. All rights reserved.

THIS SOFTWARE CONTAINS CONFIDENTIAL INFORMATION AND TRADE SECRETS OF SUN MICROSYSTEMS, INC. USE, DISCLOSURE OR REPRODUCTION IS PROHIBITED WITHOUT THE PRIOR EXPRESS WRITTEN PERMISSION OF SUN MICROSYSTEMS, INC. U.S. Government Rights - Commercial software. Government users are subject to the Sun Microsystems, Inc. standard license agreement and applicable provisions of the FAR and its supplements. Use is subject to license terms.

This distribution may include materials developed by third parties.

Sun, Sun Microsystems, the Sun logo, Java and the Sun ONE logo are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries.

UNIX is a registered trademark in the U.S. and other countries, exclusively licensed through X/Open Company, Ltd.

This product is covered and controlled by U.S. Export Control laws and may be subject to the export or import laws in other countries. Nuclear, missile, chemical biological weapons or nuclear maritime end uses or end users, whether direct or indirect, are strictly prohibited. Export or reexport to countries subject to U.S. embargo or to entities identified on U.S. export exclusion lists, including, but not limited to, the denied persons and specially designated nationals lists is strictly prohibited.

---

Copyright © 2003 Sun Microsystems, Inc., 4150 Network Circle, Santa Clara, California 95054, Etats-Unis. Tous droits réservés.

CE LOGICIEL CONTIENT DES INFORMATIONS CONFIDENTIELLES ET DES SECRETS COMMERCIAUX DE SUN MICROSYSTEMS, INC. SON UTILISATION, SA DIVULGATION ET SA REPRODUCTION SONT INTERDITES SANS L'AUTORISATION EXPRESSE, ÉCRITE ET PRÉALABLE DE SUN MICROSYSTEMS, INC. Droits du gouvernement américain, utilisateurs gouvernementaux - logiciel commercial. Les utilisateurs gouvernementaux sont soumis au contrat de licence standard de Sun Microsystems, Inc., ainsi qu'aux dispositions en vigueur de la FAR [ (Federal Acquisition Regulations) et des suppléments à celles-ci. Distribué par des licences qui en restreignent l'utilisation.

Cette distribution peut comprendre des composants développés par des tierces parties.

Sun, Sun Microsystems, le logo Sun, Java et le logo Sun ONE sont des marques de fabrique ou des marques déposées de Sun Microsystems, Inc. aux Etats-Unis et dans d'autres pays.

UNIX est une marque déposée aux Etats-Unis et dans d'autres pays et licenciée exclusivement par X/Open Company, Ltd.

Les produits qui font l'objet de ce manuel d'entretien et les informations qu'il contient sont régis par la législation américaine en matière de contrôle des exportations et peuvent être soumis au droit d'autres pays dans le domaine des exportations et importations. Les utilisations finales, ou utilisateurs finaux, pour des armes nucléaires, des missiles, des armes biologiques et chimiques ou du nucléaire maritime, directement ou indirectement, sont strictement interdites. Les exportations ou réexportations vers des pays sous embargo des États-Unis, ou vers des entités figurant sur les listes d'exclusion d'exportation américaines, y compris, mais de manière non exclusive, la liste de personnes qui font objet d'un ordre de ne pas participer, d'une façon directe ou indirecte, aux exportations des produits ou des services qui sont régi par la législation américaine en matière de contrôle des exportations ("U.S. Commerce Department's Table of Denial Orders") et la liste de ressortissants spécifiquement désignés ("U.S. Treasury Department of Specially Designated Nationals and Blocked Persons"), sont rigoureusement interdites.

# Contents

<b>About This Book</b> .....	<b>9</b>
Who Should Use This Guide .....	9
Using the Documentation .....	10
How This Guide Is Organized .....	12
Documentation Conventions .....	13
General Conventions .....	13
Conventions Referring to Directories .....	14
Product Support .....	15
<b>Chapter 1 Basics of Server Operation</b> .....	<b>17</b>
Configuration Files .....	17
server.xml .....	18
init.conf .....	18
obj.conf .....	18
mime.types .....	19
Dynamic Reconfiguration .....	19
Manually Editing Configuration Files .....	20
<b>Chapter 2 Server Configuration Files</b> .....	<b>23</b>
The sun-server_1_0.dtd File .....	24
Subelements .....	24
Data .....	25
Attributes .....	25
Elements in the server.xml File .....	26
General Elements .....	26
server .....	27
property .....	28

description	29
admin-service	29
server-instance	30
Listener Service Elements	30
http-service	30
http-listener	32
ssl	34
mime	35
acl	36
virtual-server-class	37
virtual-server	38
http-qos	43
auth-db	43
iiop-service	44
orb	45
ssl-client-config	46
iiop-listener	47
Container Elements	48
web-container	48
ejb-container	49
mdb-container	53
J2EE Service Elements	55
jms-service	55
log-service	57
security-service	59
auth-realm	60
transaction-service	62
Java Configuration Elements	64
java-config	65
profiler	67
jvm-options	68
Resource Elements	68
resources	69
custom-resource	70
external-jndi-resource	71
jdbc-resource	72
mail-resource	72
jms-resource	74
persistence-manager-factory-resource	76
jdbc-connection-pool	77
Application Elements	81
applications	81
lifecycle-module	82

j2ee-application .....	83
ejb-module .....	84
web-module .....	85
connector-module .....	86
User Database Selection .....	87
The Sun ONE LDAP Schema .....	88
The Convergence Tree .....	89
The Domain Component (dc)Tree .....	89
Variables .....	90
Format of a Variable .....	90
The id Variable .....	91
Other Important Variables .....	91
General Variables .....	91
send-cgi Variables .....	91
Variable Evaluation .....	92
Sample server.xml File .....	92
<b>Chapter 3 Syntax and Use of init.conf .....</b>	<b>97</b>
Init Functions .....	98
Server Information .....	99
NetSiteRoot .....	99
TempDir .....	99
TempDirSecurity .....	99
User (UNIX only) .....	100
DNS Lookup .....	101
AsyncDNS .....	101
DNS .....	101
Threads, Processes and Connections .....	102
ConnQueueSize .....	103
HeaderBufferSize .....	103
IOTimeout .....	103
KeepAliveThreads .....	104
KeepAliveTimeout .....	104
KernelThreads (Windows only) .....	104
ListenQ .....	105
MaxKeepAliveConnections .....	105
PostThreadsEarly .....	105
RcvBufSize .....	105
RqThrottle .....	105
RqThrottleMin .....	106
SndBufSize .....	106
StackSize .....	106
StrictHttpHeaders .....	106

TerminateTimeout	107
ThreadIncrement	107
Native Thread Pools	107
NativePoolStackSize	108
NativePoolMaxThreads	108
NativePoolMinThreads	108
NativePoolQueueSize	108
CGI	109
CGIExpirationTimeout	109
CGIStubIdleTimeout	109
MaxCGIStubs	110
MinCGIStubs	110
WincgiTimeout (Windows only)	110
Error Logging	110
ErrorLogDateFormat	110
LogFlushInterval	111
PidLog	111
ACL	112
ACLCacheLifetime	112
ACLUserCacheSize	112
ACLGroupCacheSize	112
Security	113
Security	113
SSLCacheEntries	114
SSLClientAuthDataLimit	114
SSLClientAuthTimeout	114
SSLSessionTimeout	114
SSL3SessionTimeout	114
Chunked Encoding	115
UseOutputStreamSize	115
ChunkedRequestBufferSize	115
ChunkedRequestTimeout	116
Miscellaneous	116
ChildRestartCallback	116
HTTPVersion	117
MaxRqHeaders	117
ReentrantTimeFunctions (Solaris only)	117
Umask (UNIX only)	117
<b>Chapter 4 MIME Types</b>	<b>119</b>
Introduction	119
Determining the MIME Type	120
How the Type Affects the Response	120

What Does the Client Do with the MIME Type? .....	121
Syntax of the MIME Types File .....	121
Sample MIME Types File .....	122
<b>Chapter 5 Other Configuration Files .....</b>	<b>123</b>
dbswitch.conf .....	123
Deployment Descriptors .....	125
generated. <i>instance</i> .acl .....	126
nsfc.conf .....	127
password.conf .....	128
server.policy .....	129
<b>Appendix A Time Formats .....</b>	<b>131</b>
<b>Appendix B Alphabetical List of Server Configuration Elements .....</b>	<b>133</b>
<b>Appendix C Alphabetical List of Directives in init.conf .....</b>	<b>137</b>
<b>Index .....</b>	<b>141</b>



# About This Book

The book discusses the purpose and use of the configuration files for Sun™ Open Net Environment (Sun ONE) Application Server 7, including `server.xml`, `init.conf`, and `mime.types`, and provides comprehensive lists of the elements and directives in these configuration files.

This preface contains information about the following topics:

- Who Should Use This Guide
- Using the Documentation
- How This Guide Is Organized
- Documentation Conventions
- Product Support

## Who Should Use This Guide

The intended audience for this guide is the person who administers and maintains the Sun ONE Application Server.

This guide assumes you are familiar with the following topics:

- J2EE specification
- HTTP
- HTML
- XML
- Java programming
- Java APIs as defined in servlet, JSP, EJB, and JDBC specifications

- Relational database concepts

## Using the Documentation

The Sun ONE Application Server manuals are available as online files in Portable Document Format (PDF) and Hypertext Markup Language (HTML) formats, at:

<http://docs.sun.com/>

The following table lists tasks and concepts described in the Sun ONE Application Server manuals. The left column lists the tasks and concepts, and the right column lists the corresponding manuals.

**Table 1** Sun ONE Application Server Documentation Roadmap

<b>For information about</b>	<b>See the following</b>
Late-breaking information about the software and the documentation	Release Notes
Supported platforms and environments	Platform Summary
Introduction to the application server, including new features, evaluation installation information, and architectural overview.	<i>Getting Started Guide</i>
Installing Sun ONE Application Server and its various components (sample applications, Administration interface, Sun ONE Message Queue).	<i>Installation Guide</i>
Creating and implementing J2EE applications that follow the open Java standards model on the Sun ONE Application Server 7. Includes general information about application design, developer tools, security, assembly, deployment, debugging, and creating lifecycle modules.	<i>Developer's Guide</i>
Creating and implementing J2EE applications that follow the open Java standards model for web applications on the Sun ONE Application Server 7. Discusses web application programming concepts and tasks, and provides sample code, implementation tips, and reference material.	<i>Developer's Guide to Web Applications</i>
Creating and implementing J2EE applications that follow the open Java standards model for enterprise beans on the Sun ONE Application Server 7. Discusses EJB programming concepts and tasks, and provides sample code, implementation tips, and reference material.	<i>Developer's Guide to Enterprise JavaBeans Technology</i>

**Table 1** Sun ONE Application Server Documentation Roadmap (*Continued*)

<b>For information about</b>	<b>See the following</b>
Creating clients that access J2EE applications on the Sun ONE Application Server 7	<i>Developer's Guide to Clients</i>
Creating web services	<i>Developer's Guide to Web Services</i>
J2EE features such as JDBC, JNDI, JTS, JMS, JavaMail, resources, and connectors	<i>Developer's Guide to J2EE Features and Services</i>
Creating custom NSAPI plugins	<i>Developer's Guide to NSAPI</i>
Performing the following administration tasks: <ul style="list-style-type: none"> <li>• Using the Administration interface and the command line interface</li> <li>• Configuring server preferences</li> <li>• Using administrative domains</li> <li>• Using server instances</li> <li>• Monitoring and logging server activity</li> <li>• Configuring the web server plugin</li> <li>• Configuring the Java Messaging Service</li> <li>• Using J2EE features</li> <li>• Configuring support for CORBA-based clients</li> <li>• Configuring database connectivity</li> <li>• Configuring transaction management</li> <li>• Configuring the web container</li> <li>• Deploying applications</li> <li>• Managing virtual servers</li> </ul>	<i>Administrator's Guide</i>
Editing server configuration files	<i>Administrator's Configuration File Reference</i>
Configuring and administering security for the Sun ONE Application Server 7 operational environment. Includes information on general security, certificates, and SSL/TLS encryption. HTTP server-based security is also addressed.	<i>Administrator's Guide to Security</i>

**Table 1** Sun ONE Application Server Documentation Roadmap (*Continued*)

For information about	See the following
Configuring and administering service provider implementation for J2EE CA connectors for the Sun ONE Application Server 7. Includes information about the Administration Tool, DTDs and provides sample XML files.	J2EE CA Service Provider Implementation Administrator's Guide
Migrating your applications to the new Sun ONE Application Server 7 programming model from the Netscape Application Server version 2.1, including a sample migration of an Online Bank application provided with Sun ONE Application Server	<i>Migration Guide</i>
Using Sun ONE Message Queue.	The Sun ONE Message Queue documentation at:  <a href="http://docs.sun.com/?p=/coll/S1_MessageQueue_30">http://docs.sun.com/?p=/coll/S1_MessageQueue_30</a>

## How This Guide Is Organized

This book has the following chapters and appendices:

- Chapter 1, “Basics of Server Operation”

This chapter introduces the major configuration files that control the Sun ONE Application Server and describes how to activate and edit them.

- Chapter 2, “Server Configuration Files”

This chapter discusses the `server.xml` file, which controls most aspects of server operation.

- Chapter 3, “Syntax and Use of `init.conf`”

This chapter discusses the directives you can set in the `init.conf` file to configure the Sun ONE Application Server during initialization.

- Chapter 4, “MIME Types”

This appendix discusses the MIME types file, which maps file extensions to file types.

- Chapter 5, “Other Configuration Files”

This chapter lists other important configuration files and provides a quick reference of their contents.

- Appendix A, “Time Formats”

This appendix describes the format strings used for dates and times in the server log.

- Appendix B, “Alphabetical List of Server Configuration Elements”
- Appendix C, “Alphabetical List of Directives in `init.conf`”

These appendices provide alphabetical lists for easy lookup of elements in `server.xml` and directives in `init.conf`.

## Documentation Conventions

This section describes the types of conventions used throughout this guide:

- General Conventions
- Conventions Referring to Directories

### General Conventions

The following general conventions are used in this guide:

- **File and directory paths** are given in UNIX<sup>®</sup> format (with forward slashes separating directory names). For Windows versions, the directory paths are the same, except that backslashes are used to separate directories.

- **URLs** are given in the format:

`http://server.domain/path/file.html`

In these URLs, *server* is the server name where applications are run; *domain* is your Internet domain name; *path* is the server’s directory structure; and *file* is an individual filename. Italic items in URLs are placeholders.

- **Font conventions** include:
  - The `monospace` font is used for sample code and code listings, API and language elements (such as function names and class names), file names, pathnames, directory names, and HTML tags.
  - *Italic* type is used for code variables.

- *Italic* type is also used for book titles, emphasis, variables and placeholders, and words used in the literal sense.
- **Bold** type is used as either a paragraph lead-in or to indicate words used in the literal sense.
- **Installation root directories** for most platforms are indicated by *install\_dir* in this document. Exceptions are noted in “Conventions Referring to Directories” on page 14.

By default, the location of *install\_dir* on **most** platforms is:

- Solaris 8 non-package-based Evaluation installations:

*user's home directory/sun/appserver7*

- Solaris unbundled, non-evaluation installations:

*/opt/SUNWappserver7*

- Windows, all installations:

*C:\Sun\AppServer7*

For the platforms listed above, *default\_config\_dir* and *install\_config\_dir* are identical to *install\_dir*. See “Conventions Referring to Directories” on page 14 for exceptions and additional information.

- **Instance root directories** are indicated by *instance\_dir* in this document, which is an abbreviation for the following:  
*default\_config\_dir/domains/domain/instance*
- **UNIX-specific descriptions** throughout this manual apply to the Linux operating system as well, except where Linux is specifically mentioned.

## Conventions Referring to Directories

By default, when using the Solaris 8 and 9 package-based installation and the Solaris 9 bundled installation, the application server files are spread across several root directories. These directories are described in this section.

- **For Solaris 9 bundled installations**, this guide uses the following document conventions to correspond to the various default installation directories provided:
  - *install\_dir* refers to */usr/appserver/*, which contains the static portion of the installation image. All utilities, executables, and libraries that make up the application server reside in this location.

- *default\_config\_dir* refers to `/var/appserver/domains`, which is the default location for any domains that are created.
- *install\_config\_dir* refers to `/etc/appserver/config`, which contains installation-wide configuration information such as licenses and the master list of administrative domains configured for this installation.
- **For Solaris 8 and 9 package-based, non-evaluation, unbundled installations**, this guide uses the following document conventions to correspond to the various default installation directories provided:
  - *install\_dir* refers to `/opt/SUNWappserver7`, which contains the static portion of the installation image. All utilities, executables, and libraries that make up the application server reside in this location.
  - *default\_config\_dir* refers to `/var/opt/SUNWappserver7/domains` which is the default location for any domains that are created.
  - *install\_config\_dir* refers to `/etc/opt/SUNWappserver7/config`, which contains installation-wide configuration information such as licenses and the master list of administrative domains configured for this installation.

## Product Support

If you have problems with your system, contact customer support using one of the following mechanisms:

- The online support web site at:

<http://www.sun.com/supporttraining/>

- The telephone dispatch number associated with your maintenance contract

Please have the following information available prior to contacting support. This helps to ensure that our support staff can best assist you in resolving problems:

- Description of the problem, including the situation where the problem occurs and its impact on your operation
- Machine type, operating system version, and product version, including any patches and other software that might be affecting the problem
- Detailed steps on the methods you have used to reproduce the problem
- Any error logs or core dumps



# Basics of Server Operation

The configuration and behavior of Sun ONE Application Server is determined by a set of configuration files. When you use the Administration interface, you change the settings in these configuration files. You can also manually edit these files.

This chapter has the following sections:

- Configuration Files
- Dynamic Reconfiguration
- Manually Editing Configuration Files

## Configuration Files

The configuration and operation of the Sun ONE Application Server is controlled by configuration files. The configuration files reside in the directory *instance\_dir/config*. This directory contains various configuration files for controlling different components. The exact number and names of configuration files depends on which components have been enabled or loaded into the server.

However, this directory always contains four configuration files that are essential for the server to operate. These files are:

- `server.xml` -- contains most of the server configuration.
- `init.conf` -- contains global server initialization information.
- `obj.conf` -- contains instructions for handling HTTP requests from clients.
- `mime.types` -- contains information for determining the content type of requested resources.

For information about other important configuration files, see Chapter 5, “Other Configuration Files”.

## server.xml

This file contains most of the server configuration. A schema file, `sun-server_1_0.dtd`, defines its format and content.

For more information about how the server uses `sun-server_1_0.dtd` and `server.xml`, see Chapter 2, “Server Configuration Files”.

## init.conf

This file sets values of variables that configure the server during initialization. The server looks at this file and executes the settings on startup. The server does not look at this file again until it is restarted.

See Chapter 3, “Syntax and Use of `init.conf`” for a list of all the variables and `Init` directives that can be set in `init.conf`.

## obj.conf

This file contains instructions for the server about how to process HTTP requests from clients and service web server content such as native server plugins and CGI programs. The server looks at the configuration defined by this file every time it processes a request from a client.

All `obj.conf` files are located in the `instance_dir/config` directory. There is one `obj.conf` file for each virtual server, unless several virtual servers are configured to share an `obj.conf` file. Whenever this guide refers to “the `obj.conf` file,” it refers to all `obj.conf` files or to the `obj.conf` file for the virtual server being described.

The file named `obj.conf` that lacks a prefix is a template that Sun ONE Application Server uses to create `obj.conf` files for each virtual server. Editing this file does not affect any existing virtual servers, but does affect any subsequently created virtual servers.

By default, each active `obj.conf` file is named `virtual_server_name-obj.conf`. Because the default virtual server for a server instance is named after the instance, when you first create a server instance, its `obj.conf` file is named `instance_name-obj.conf`. Editing one of these files directly or through the Administration interface changes the configuration of a virtual server.

The `obj.conf` file is essential to the operation of the Sun ONE Application Server. When you make changes to the server through the Administration interface, the system automatically updates `obj.conf`.

The file `obj.conf` contains a series of instructions (directives) that tell the Sun ONE Application Server what to do at each stage in the request-response process.

For information about how the server uses `obj.conf`, see the *Sun ONE Application Server Developer's Guide to NSAPI*.

## mime.types

This file maps file extensions to MIME types to enable the server to determine the content type of a requested resource. For example, requests for resources with `.html` extensions indicate that the client is requesting an HTML file, while requests for resources with `.gif` extensions indicate that the client is requesting an image file in GIF format.

For more information about how the server uses `mime.types`, see Chapter 4, “MIME Types”.

# Dynamic Reconfiguration

You do not have to restart the server for changes to these files to take effect:

- `obj.conf`
- `mime.types`
- ACL files
- `server.xml` (applications and resources subelements only)

However, with the exception of deployment, you must apply the changes for those changes to take effect. You can use the Administration interface as follows:

1. Go to the server instance page.
2. Select the General tab.
3. Select the Apply Changes button.

Or you can use the command line as follows:

```
asadmin reconfig --user user [--password password] [--passwordfile password_file]  
[--host machine] [--port port] [--discardmanualchanges=false |  
--keepmanualchanges=false] instance_name
```

For example:

```
asadmin reconfig --user joeuser --password secret --keepmanualchanges=true  
server1
```

When you change the configuration and apply the changes, the new configuration that contains all the information from the dynamically configurable files is loaded into memory.

---

**NOTE** Sometimes when you apply configuration changes, the server instance displays an error message. For example, when security is turned on and you apply changes, you may see an `Invalid configuration error`.

If this happens, restart the instance as soon as a restart message such as `Instance restart is required` or `Server restart needed` is displayed. Deferring the restart may cause similar error messages to be shown repeatedly.

---

## Manually Editing Configuration Files

Manually editing configuration files is not recommended. Here are some cautionary guidelines for manually editing configuration files:

- Edit only the files in the `instance_dir/config` directory. Do not copy files to the backup directory or remove the timestamp files (which prevent overwriting of manual changes).
- If you have made both manual changes and changes through the Administration interface without applying them, you have the following alternatives:
  - Apply the changes using the Administration interface, which forces you to choose between your manual and Administration interface changes.
  - Use the `--keepmanualchanges` or `--discardmanualchanges` option of the `asadmin reconfig` command to make the same choice at the command line. For example:

```
asadmin reconfig --user joeuser --password secret --keepmanualchanges=true  
server1
```

To avoid this dilemma, always apply changes immediately after making them, and don't mix manual and Administration interface changes.

- Do not manually edit a file and then restart the server. Use the `--keepmanualchanges` option of the `asadmin reconfig` command before restarting the server. See the example above.
- Whenever the configuration in `server.xml` is modified using the Administration interface, it is always validated against the `sun-server_1_0.dtd` file. Additional validation is done that pertains to checking the file's cross-references. Make sure your configuration is complete and correct before applying it.
- When you modify `applications` or `resources` subelements of `server.xml` (for example, you deploy a J2EE application or register a JDBC Connection Pool), the Administration Server attempts to apply the changes to a running server instance. Make sure your configuration is complete and correct before applying it.
- The Administration Server remembers unapplied changes across its own restarts. Therefore, at times the Administration Server may have a view of a server instance's configuration that is not the same as the actual configuration of the server instance.



# Server Configuration Files

The `server.xml` file contains most of the server configuration. The encoding is UTF-8 to maintain compatibility with regular UNIX text editors. The `server.xml` file is located in the `instance_dir/config` directory. A schema file, `sun-server_1_0.dtd`, determines the format and content of the `server.xml` file.

This chapter describes `server.xml` and `sun-server_1_0.dtd` in these sections:

- The `sun-server_1_0.dtd` File
- Elements in the `server.xml` File
- General Elements
- Listener Service Elements
- Container Elements
- J2EE Service Elements
- Java Configuration Elements
- Resource Elements
- Application Elements
- User Database Selection
- The Sun ONE LDAP Schema
- Variables
- Sample `server.xml` File

---

**NOTE** Virtual servers are not the same thing as server instances. Each server instance is a completely separate server that contains one or more virtual servers.

---

## The sun-server\_1\_0.dtd File

The `sun-server_1_0.dtd` file defines the structure of the `server.xml` file, including the elements it can contain and the subelements and attributes these elements can have. The `sun-server_1_0.dtd` file is located in the `install_dir/lib/dtds` directory.

---

**NOTE** Do not edit the `sun-server_1_0.dtd` file; its contents change only with new versions of Sun ONE Application Server.

---

---

**NOTE** The `sun-server_1_0.dtd` interface is Unstable. An unstable interface may be experimental or transitional, and hence may change incompatibly, be removed, or be replaced by a more stable interface in the next release.

---

For general information about DTD files and XML, see the XML specification at:

<http://www.w3.org/TR/REC-xml>

Each element defined in a DTD file (which may be present in the corresponding XML file) can contain the following:

- Subelements
- Data
- Attributes

## Subelements

Elements can contain subelements. For example, the following file fragment defines the `iiop-listener` element.

```
<!ELEMENT iiop-listener (ssl?, property*)>
```

The `ELEMENT` tag specifies that an `iiop-listener` element can contain `ssl` and `property` elements in that order.

The following table shows how optional suffix characters of subelements determine the requirement rules, or number of allowed occurrences, for the subelements. The left column lists the subelement ending character, and the right column lists the corresponding requirement rule.

**Table 2-1** requirement rules and subelement suffixes

Subelement Suffix	Requirement Rule
<i>element*</i>	Can contain <i>zero or more</i> of this subelement.
<i>element?</i>	Can contain <i>zero or one</i> of this subelement.
<i>element+</i>	Must contain <i>one or more</i> of this subelement.
<i>element</i> (no suffix)	Must contain <i>only one</i> of this subelement.

If an element cannot contain other elements, you see `EMPTY` or `(#PCDATA)` instead of a list of element names in parentheses.

## Data

Some elements contain character data instead of subelements. These elements have definitions of the following format:

```
<!ELEMENT element-name (#PCDATA)>
```

For example:

```
<!ELEMENT description (#PCDATA)>
```

In the `server.xml` file, white space is treated as part of the data in a data element. Therefore, there should be no extra white space before or after the data delimited by a data element. For example:

```
<description>shopping cart bean</description>
```

## Attributes

Elements that have `ATTLIST` tags contain attributes (name-value pairs). For example:

```
<!ATTLIST iiop-listener      id          CDATA      #REQUIRED
                             address     CDATA      #REQUIRED
                             port        CDATA      "3700"
                             enabled     %boolean;  "true">
```

An `iiop-listener` element can contain `id`, `address`, `port`, and `enabled` attributes.

The #REQUIRED label means that a value must be supplied. The #IMPLIED label means that the attribute is optional, and that Sun ONE Application Server generates a default value. Wherever possible, explicit defaults for optional attributes (such as "true") are listed.

Attribute declarations specify the type of the attribute. For example, CDATA means character data, and %boolean is a predefined enumeration.

## Elements in the server.xml File

This section describes the XML elements in the `server.xml` file. Elements are grouped as follows:

- General Elements
- Listener Service Elements
- Container Elements
- J2EE Service Elements
- Java Configuration Elements
- Resource Elements
- Application Elements

---

**NOTE** Subelements must be defined in the order in which they are listed under each **Subelements** heading unless otherwise noted.

---

For an alphabetical listing of elements in `server.xml`, see Appendix B, “Alphabetical List of Server Configuration Elements”.

## General Elements

General elements are as follows:

- `server`
- `property`
- `description`

- `admin-service`
- `server-instance`

## server

Defines a server. This is the root element; there can only be one `server` element in a `server.xml` file.

### Subelements

The following table describes subelements for the `server` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-2** `server` subelements

Element	Required	Description
<code>http-service</code>	only one	Defines the HTTP service.
<code>iiop-service</code>	only one	Defines the IIOP service.
<code>admin-service</code>	zero or one	Not implemented.
<code>web-container</code>	only one	Configures the web container.
<code>ejb-container</code>	only one	Configures the EJB container.
<code>mdb-container</code>	only one	Configures the message-driven bean (MDB) container.
<code>jms-service</code>	only one	Configures the Java Message Service provider.
<code>log-service</code>	only one	Configures the system logging service.
<code>security-service</code>	only one	Defines information needed by the J2EE security service.
<code>transaction-service</code>	only one	Configures the Java Transaction Service.
<code>java-config</code>	only one	Contains the JVM configuration.
<code>resources</code>	only one	Contains configured resources.
<code>applications</code>	only one	Contains deployed J2EE applications, J2EE modules, and Lifecycle modules.
<code>property</code>	zero or more	Specifies a property or a variable.

### Attributes

The following table describes attributes for the `server` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-3** `server` attributes

Attribute	Default	Description
<code>name</code>	<code>none</code>	Specifies the name of the server instance.
<code>locale</code>	<code>operating system default</code>	(optional) Specifies the server instance language.
<code>log-root</code>	<code>instance_dir/logs</code>	(optional) Specifies where the server instance's log files are kept. The directory in which the server log is kept must be writable by whatever user account the server runs as. See the <code>log-service</code> description for details about logs.
<code>application-root</code>	<code>instance_dir/applications</code>	(optional) Specifies the absolute path where deployed applications reside for this server instance.
<code>session-store</code>	<code>instance_dir/session-store</code>	(optional) Specifies the directory where passivated beans are stored in the file system.

### property

Specifies a property, or a variable that is defined in `server.xml` and referenced in `obj.conf`. For information about variables, see “Variables” on page 90.

A property adds configuration information to its parent element that is one or both of the following:

- Optional with respect to Sun ONE Application Server
- Needed by a system or object that Sun ONE Application Server doesn't have knowledge of, such as an LDAP server or a Java class

For example, an `auth-realm` element can include `property` subelements:

```
<auth-realm name="file"
  classname="com.iplanet.ias.security.auth.realm.file.FileRealm">
  <property name="file" value="instance_dir/config/keyfile"/>
  <property name="jaas-context" value="fileRealm"/>
</auth-realm>
```

Which properties an `auth-realm` element uses depends on the value of the `auth-realm` element's `name` attribute. The `file` realm uses `file` and `jaas-context` properties. Other realms use different properties.

### Subelements

The following table describes subelements for the `property` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-4** `property` subelements

Element	Required	Description
<code>description</code>	zero or one	Contains a text description of this element.

### Attributes

The following table describes attributes for the `property` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-5** `property` attributes

Attribute	Default	Description
<code>name</code>	<code>none</code>	Specifies the name of the property or variable.
<code>value</code>	<code>none</code>	Specifies the value of the property or variable.

## description

Contains a text description of the parent element.

### Subelements

`none`

### Attributes

`none`

## admin-service

This element is not implemented and should not be used.

## **server-instance**

This element is not implemented and should not be used.

# Listener Service Elements

Listener service elements are as follows:

- `http-service`
- `http-listener`
- `ssl`
- `mime`
- `acl`
- `virtual-server-class`
- `virtual-server`
- `http-qos`
- `auth-db`
- `iiop-service`
- `iiop-listener`
- `orb`

## **http-service**

Defines the HTTP service.

For more information about the quality of service features defined in this element's attributes, see the *Sun ONE Application Server Performance Tuning, Sizing, and Scaling Guide*.

### **Subelements**

The following table describes subelements for the `http-service` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-6** http-service subelements

Element	Required	Description
http-listener	zero or more	Defines an HTTP listen socket.
mime	zero or more	Defines MIME types.
acl	zero or more	References an ACL file.
virtual-server-class	zero or more	Defines a virtual server class.
http-qos	zero or one	Defines quality of service parameters.
property	zero or more	Specifies a property or a variable.

---

**NOTE** The `http-listener`, `mime`, `acl`, and `virtual-server-class` elements can occur in any order, but `http-qos` and `property` elements must occur second to last and last, respectively.

---

### Attributes

The following table describes attributes for the `http-service` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-7** http-service attributes

Attribute	Default	Description
qos-metrics-interval-in-seconds	30	(optional) Specifies the interval during which traffic is measured.
qos-recompute-time-interval-in-millis	100	(optional) Specifies the period in which the bandwidth gets recomputed for all server entities.
qos-enabled	true	(optional) Enables quality of service features, which let you set limits on server entities or view server statistics for bandwidth and connections. Allowed values are <code>yes</code> , <code>no</code> , <code>on</code> , <code>off</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .

## http-listener

Defines an HTTP listen socket.

---

**NOTE** When you create a secure listener through the Administration interface, security is automatically turned on globally in `init.conf`. When you create a secure listener manually in `server.xml`, you must manually turn on security by editing the `init.conf` file's `Security` directive.

---

### Subelements

The following table describes subelements for the `http-listener` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-8** `http-listener` subelements

Element	Required	Description
<code>ssl</code>	zero or one	Defines SSL parameters.

### Attributes

The following table describes attributes for the `http-listener` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-9** `http-listener` attributes

Attribute	Default	Description
<code>id</code>	<code>none</code>	The unique listener name. An <code>http-listener</code> name cannot begin with a number.
<code>address</code>	<code>none</code>	IP address of the listener. Can be in dotted-pair or IPv6 notation. Can be <code>any</code> (for <code>INADDR_ANY</code> ) to listen on all IP addresses. Can be a hostname.
<code>port</code>	<code>none</code>	Port number on which the listener listens. Legal values are 1 - 65535. On UNIX, creating sockets that listen on ports 1 - 1024 requires superuser privileges. Configuring an SSL listener to listen on port 443 is recommended.

**Table 2-9** http-listener attributes

Attribute	Default	Description
family	inet	(optional) The socket family type. Legal values are <code>inet</code> , <code>inet6</code> , and <code>nca</code> . Use the value <code>inet6</code> for IPv6 listeners. If this value is <code>inet6</code> , IPv4 addresses are prefixed with <code>::ffff:</code> in the server log. Specify <code>nca</code> to make use of the Solaris Network Cache and Accelerator.
acceptor-threads	1	(optional) Number of acceptor threads for the listener. The recommended value is the number of processors in the machine. Legal values are 1 - 1024.
blocking-enabled	false	(optional) Determines whether the listener and the accepted socket are put in to blocking mode. Use of blocking mode may improve benchmark scores. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .
security-enabled	false	(optional) Determines whether the listener runs SSL. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> . You can turn SSL2 or SSL3 on or off and set ciphers using an <code>ssl</code> element.  The <code>Security</code> setting in the <code>init.conf</code> file globally enables or disables SSL by making certificates available to the server instance. Therefore, <code>Security</code> in <code>init.conf</code> must be <code>on</code> or <code>security-enabled</code> in <code>server.xml</code> does not work. For more information, see Chapter 3, “Syntax and Use of <code>init.conf</code> ”.
default-virtual-server	none	The <code>id</code> attribute of the default virtual server for this particular listener.
server-name	none	Tells the server what to put in the host name section of any URLs it sends to the client. This affects URLs the server automatically generates; it doesn't affect the URLs for directories and files stored in the server. This name should be the alias name if your server uses an alias.  If you append a colon and port number, that port will be used in URLs the server sends to the client.
enabled	true	(optional) Determines whether the listener is active. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .

---

**CAUTION** Blocking mode sockets should not be used in real world deployments. Use of blocking mode sockets precludes dynamic reconfiguration and exposes the server to denial of service attacks.

---

## ssl

Defines SSL (Secure Socket Layer) parameters.

An `ssl` element is required inside an `http-listener` element that has its `security-enabled` attribute set to `on`.

An `ssl` element is only allowed inside an `http-listener` or `iiop-listener` element.

### Subelements

none

### Attributes

The following table describes attributes for the `ssl` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-10** `ssl` attributes

Attribute	Default	Description
<code>cert-nickname</code>	none	The nickname of the server certificate in the certificate database or the PKCS#11 token. In the certificate, the name format is <i>tokenname: nickname</i> . Including the <i>tokenname:</i> part of the name in this attribute is optional.
<code>ssl2-enabled</code>	false	(optional) Determines whether SSL2 is enabled. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .  If both SSL2 and SSL3 are enabled for a virtual server, the server tries SSL3 encryption first. If that fails, the server tries SSL2 encryption.
<code>ssl2-ciphers</code>	none	(optional) A comma-separated list of the SSL2 ciphers used, with the prefix <code>+</code> to enable or <code>-</code> to disable, for example <code>+rc4</code> . Allowed values are <code>rc4</code> , <code>rc4export</code> , <code>rc2</code> , <code>rc2export</code> , <code>idea</code> , <code>des</code> , <code>desede3</code> .

**Table 2-10** ssl attributes

Attribute	Default	Description
ssl3-enabled	true	(optional) Determines whether SSL3 is enabled. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> . The default is <code>true</code> .  If both SSL2 and SSL3 are enabled for a virtual server, the server tries SSL3 encryption first. If that fails, the server tries SSL2 encryption.
ssl3-tls-ciphers	none	(optional) A comma-separated list of the SSL3 ciphers used, with the prefix <code>+</code> to enable or <code>-</code> to disable, for example <code>+rsa_des_sha</code> . Allowed SSL3 values are <code>rsa_rc4_128_md5</code> , <code>rsa_3des_sha</code> , <code>rsa_des_sha</code> , <code>rsa_rc4_40_md5</code> , <code>rsa_rc2_40_md5</code> , <code>rsa_null_md5</code> . Allowed TLS values are <code>rsa_des_56_sha</code> , <code>rsa_rc4_56_sha</code> .
tls-enabled	true	(optional) Determines whether TLS is enabled. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .
tls-rollback-enabled	true	(optional) Determines whether TLS rollback is enabled. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> . TLS rollback should be enabled for Microsoft Internet Explorer 5.0 and 5.5. For more information, see the <i>Sun ONE Application Server Administrator's Guide</i> .
client-auth-enabled	false	(optional) Determines whether SSL3 client authentication is performed on every request, independent of ACL-based access control. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .

## mime

Defines MIME types.

The most common way that the server determines the MIME type of a requested resource is by invoking the `type-by-extension` directive in the `ObjectType` section of the `obj.conf` file. The `type-by-extension` function does not work if no `mime` element has been defined in the `server` element.

---

**NOTE** The `mime.types` interface is Unstable. An unstable interface may be experimental or transitional, and hence may change incompatibly, be removed, or be replaced by a more stable interface in the next release.

---

### Subelements

none

### Attributes

The following table describes attributes for the `mime` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-11** `mime` attributes

Attribute	Default	Description
<code>id</code>	none	Internal name for the MIME types listing. Used in a <code>virtual-server</code> element to define the MIME types used by the virtual server. The MIME types name cannot begin with a number.
<code>file</code>	none	The name of a MIME types file. For information about the format of this file, see Chapter 4, “MIME Types”.

---

## **acl**

References an ACL file.

---

**NOTE** The ACL file interface is Unstable. An unstable interface may be experimental or transitional, and hence may change incompatibly, be removed, or be replaced by a more stable interface in the next release.

---

### Subelements

none

### Attributes

The following table describes attributes for the `acl` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-12** `acl` attributes

Attribute	Default	Description
<code>id</code>	<code>none</code>	Internal name for the ACL file listing. Used in a <code>virtual-server</code> element to define the ACL file used by the virtual server. An ACL file listing name cannot begin with a number.
<code>file</code>	<code>none</code>	An ACL file. Each ACL file must have a unique name. For information about the format of an ACL file, see the <i>Sun ONE Application Server Administrator's Guide to Security</i> .

## virtual-server-class

Defines a virtual server class.

### Subelements

The following table describes subelements for the `virtual-server-class` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-13** `virtual-server-class` subelements

Element	Required	Description
<code>virtual-server</code>	zero or more	Defines a virtual server.
<code>http-qos</code>	zero or one	Defines quality of service parameters.
<code>property</code>	zero or more	Specifies a property or a variable.

### Attributes

The following table describes attributes for the `virtual-server-class` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-14** `virtual-server-class` attributes

Attribute	Default	Description
<code>id</code>	<code>none</code>	Virtual server class ID. This is a unique ID that allows lookup of a specific virtual server class. A virtual server class ID cannot begin with a number.

**Table 2-14** `virtual-server-class` attributes

Attribute	Default	Description
<code>config-file</code>	<code>none</code>	(optional) The file name of the <code>obj.conf</code> file for this class of virtual servers. Can be overridden in a <code>virtual-server</code> element.
<code>default-object</code>	<code>default</code>	(optional) Tells the server which object loaded from an <code>obj.conf</code> file is the default. Can be overridden in a <code>virtual-server</code> element.  The default object is expected to have all the name translation ( <code>NameTrans</code> ) directives for the virtual server; any server behavior that is configured in the default object affects the entire virtual server class.  If you specify an object that doesn't exist, the server doesn't report an error until a client tries to retrieve a document. The Administration interface assumes the default to be the object named <code>default</code> . Don't deviate from this convention if you use (or plan to use) the Administration interface.
<code>accept-language</code>	<code>false</code>	(optional) If <code>true</code> , the server parses the <code>Accept-Language</code> header and sends an appropriate language version based on which language the client can accept. You should set this value to <code>true</code> only if the server supports multiple languages. Can be overridden in a <code>virtual-server</code> element. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> . Can be overridden in a <code>virtual-server</code> element.
<code>enabled</code>	<code>true</code>	(optional) Determines whether the virtual server class is active. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .

## virtual-server

Defines a virtual server. A virtual server, also called a virtual host, is a virtual web server that serves content targeted for a specific URL. Multiple virtual servers may serve content using the same or different host names, port numbers, or IP addresses. The HTTP service can direct incoming web requests to different virtual servers based on the URL.

When you first install Sun ONE Application Server, a default virtual server is created. (You can also assign a default virtual server to each new `http-listener` you create.)

---

**NOTE** Virtual servers are not the same thing as server instances. Each server instance is a completely separate server that contains one or more virtual servers.

---

Before the Sun ONE Application Server can process a request, it must accept the request via a listener, then direct the request to the correct virtual server. The virtual server is determined as follows:

- If the listener is configured to only a default virtual server, that virtual server is selected.
- If the listener has more than one virtual server configured to it, the request `Host` header is matched to the `hosts` attribute of a virtual server. If no `Host` header is present or no `hosts` attribute matches, the default virtual server for the listener is selected.

If a virtual server is configured to an SSL listener, its `hosts` attribute is checked against the subject pattern of the certificate at server startup, and a warning is generated and written to the server log if they don't match.

### Subelements

The following table describes subelements for the `virtual-server` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-15** `virtual-server` subelements

Element	Required	Description
<code>http-qos</code>	zero or one	Defines quality of service parameters.
<code>auth-db</code>	zero or more	Defines the user database for the virtual server; not applicable to J2EE applications.
<code>property</code>	zero or more	Specifies a property or a variable.

### Attributes

The following table describes attributes for the `virtual-server` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-16** `virtual-server` attributes

Attribute	Default	Description
<code>id</code>	<code>none</code>	Virtual server ID. This is a unique ID that allows lookup of a specific virtual server. Can also be referred to as the variable <code>\$id</code> in an <code>obj.conf</code> file. A virtual server ID cannot begin with a number.
<code>http-listeners</code>	<code>none</code>	(optional) A comma-separated list of <code>http-listener</code> ids that specify the connection(s) the virtual server uses. Required only for a <code>virtual-server</code> that is not the <code>default-virtual-server</code> of an <code>http-listener</code> .
<code>default-web-module</code>	<code>none</code>	(optional) The default <code>web-module</code> for this virtual server, which responds to all requests that cannot be resolved to other web modules deployed to this virtual server.  If this attribute is empty, the <code>web-module</code> assigned to this virtual server that has an empty <code>context-root</code> attribute is used. If no <code>web-module</code> assigned to this virtual server has an empty <code>context-root</code> , the system default web module is used.
<code>config-file</code>	<code>virtual_server_name-obj.conf</code>	(optional) The file name of the <code>obj.conf</code> file for this virtual server. Can override the value in a <code>virtual-server-class</code> element.

**Table 2-16** `virtual-server` attributes

Attribute	Default	Description
<code>default-object</code>	<code>default</code>	<p>(optional) Tells the server which object loaded from an <code>obj.conf</code> file is the default. Can override the value in a <code>virtual-server-class</code> element.</p> <p>The default object is expected to have all the name translation (<code>NameTrans</code>) directives for the virtual server; any server behavior that is configured in the default object affects the entire server. The default value is <code>default</code>.</p> <p>If you specify an object that doesn't exist, the server doesn't report an error until a client tries to retrieve a document. The Administration interface assumes the default to be the object named <code>default</code>. Don't deviate from this convention if you use (or plan to use) the Administration interface.</p>
<code>hosts</code>	<code>none</code>	<p>A comma-separated list of values allowed in the <code>Host</code> request header to select the current virtual server. Each <code>virtual-server</code> that is configured to the same <code>http-listener</code> must have a unique <code>hosts</code> value for that listener.</p>
<code>mime</code>	<code>none</code>	<p>The <code>id</code> of the <code>mime</code> element used by the virtual server.</p>
<code>state</code>	<code>on</code>	<p>(optional) Determines whether a <code>virtual-server</code> is active (<code>on</code>) or inactive (<code>off</code>, <code>disabled</code>). The default is <code>on</code> (active). When inactive, a <code>virtual-server</code> does not service requests.</p> <p>If a <code>virtual-server</code> is disabled, only the global server administrator can turn it <code>on</code>.</p>
<code>acls</code>	<code>none</code>	<p>(optional) One or more <code>id</code> attributes of <code>acl</code> elements, separated by commas. Specifies the ACL file(s) used by the virtual server.</p>

**Table 2-16** virtual-server attributes

Attribute	Default	Description
accept-language	false	(optional) If true, the server parses the Accept-Language header and sends an appropriate language version based on which language the client can accept. You should set this value to on only if the server supports multiple languages. Legal values are on, off, yes, no, 1, 0, true, false. Can override the value in a virtual-server-class element.
log-file	server.log in the directory specified by the log-root attribute of the server element	(optional) Writes this virtual server's log messages to a log file separate from the server log. The file and directory in which the virtual server log is kept must be writable by whatever user account the server runs as. See the log-service description for details about logs.

### Properties

The following table describes properties for the virtual-server element. The left column lists the property name, the middle column indicates the default value if the property is omitted, and the right column describes what the property does.

**Table 2-17** virtual-server properties

Property	Default	Description
sso-enabled	true	If true, single sign-on is enabled for web applications on this virtual server that are configured for the same realm. If false, single sign-on is disabled for this virtual server, and users must authenticate separately to every application on the virtual server. Legal values are on, off, yes, no, 1, 0, true, false.
sso-max-inactive-seconds	300	Specifies the time after which a user's single sign-on record becomes eligible for purging if no client activity is received. Since single sign-on applies across several applications on the same virtual server, access to any of the applications keeps the single sign-on record active. Higher values provide longer single sign-on persistence for the users at the expense of more memory use on the server.
sso-reap-interval-seconds	60	Specifies the interval between purges of expired single sign-on records.

## http-qos

Defines quality of service parameters of an `http-service`, `virtual-server-class`, or `virtual-server` element.

Attributes in the `http-service` element activate the quality of service features.

For more information, see the *Sun ONE Application Server Performance Tuning, Sizing, and Scaling Guide*.

### Subelements

none

### Attributes

The following table describes attributes for the `http-qos` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-18** `http-qos` attributes

Attribute	Default	Description
<code>bandwidth-limit</code>	none	(required if <code>enforce-bandwidth-limit</code> is true) The maximum bandwidth limit for the server, <code>virtual-server-class</code> , or <code>virtual-server</code> in bytes per second.
<code>enforce-bandwidth-limit</code>	false	(optional) Specifies whether the bandwidth limit should be enforced or not. Allowed values are yes, no, on, off, 1, 0, true, false.
<code>connection-limit</code>	none	(required if <code>enforce-connection-limit</code> is true) The maximum number of concurrent connections for the server, <code>virtual-server-class</code> , or <code>virtual-server</code> .
<code>enforce-connection-limit</code>	false	(optional) Specifies whether the connection limit should be enforced or not. Allowed values are yes, no, on, off, 1, 0, true, false.

## auth-db

Defines the user database used by the `virtual-server`; not applicable to J2EE applications.

See “User Database Selection” on page 87 for more information about how a user database is selected for a given virtual server.

---

**NOTE** The user database applies only to the security of the server itself. It is not related to J2EE application and module security. For more information, see the *Sun ONE Application Server Administrator's Guide to Security*.

---

**Subelements**

none

**Attributes**

The following table describes attributes for the `auth-db` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-19** `auth-db` attributes

Attribute	Default	Description
<code>id</code>	none	The user database name in the virtual server's ACL file. A user database name cannot begin with a number.
<code>database</code>	none	The user database name in the <code>dbswitch.conf</code> file.
<code>basedn</code>	none	(optional) Overrides the base DN lookup in the <code>dbswitch.conf</code> file. However, the <code>basedn</code> value is still relative to the base DN value from the <code>dbswitch.conf</code> entry.
<code>certmaps</code>	none	(optional) Specifies which certificate to LDAP entry mappings (defined in <code>certmap.conf</code> ) to use. If not present, all mappings are used. All lookups based on mappings in <code>certmap.conf</code> are relative to the final base DN of the <code>virtual-server</code> .

---

**iiop-service**

Defines the IIOP service.

**Subelements**

The following table describes subelements for the `iiop-service` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-20** `iiop-service` subelements

Element	Required	Description
<code>orb</code>	only one	Configures the ORB.
<code>ssl-client-config</code>	zero or one	Defines SSL parameters for the ORB.
<code>iiop-listener</code>	zero or more	Defines an IIOP listen socket.

**Attributes**

none

**orb**

Configures the ORB.

To enable SSL for outbound connections, include an `ssl-client-config` subelement in the parent `iiop-service` element.

**Subelements**

The following table describes subelements for the `orb` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-21** `orb` subelements

Element	Required	Description
<code>property</code>	zero or more	Specifies a property or a variable.

**Attributes**

The following table describes attributes for the `orb` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-22** `orb` attributes

Attribute	Default	Description
<code>message-fragment-size</code>	1024	(optional) GIOPv1.2 messages larger than this number of bytes are fragmented.

**Table 2-22** orb attributes

Attribute	Default	Description
steady-thread-pool-size	10	(optional) The minimum number of worker threads in the ORB.
max-thread-pool-size	200	(optional) The maximum number of worker threads in the ORB.
idle-thread-timeout-in-seconds	300	(optional) Idle worker threads are removed from the pool after this amount of time.
max-connections	1024	(optional) The maximum number of incoming connections on all IIOP listeners. Legal values are integers.
log-level	Value of level attribute of log-service element	(optional) Controls the type of messages logged by this element to the server log. For details, see the description of the level attribute of the log-service element.
monitoring-enabled	false	(optional) Determines whether monitoring of the ORB is enabled. Legal values are on, off, yes, no, 1, 0, true, false.

## ssl-client-config

Defines SSL parameters for the ORB when it makes outbound SSL connections and behaves as a client.

### Subelements

The following table describes subelements for the `ssl-client-config` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-23** `ssl-client-config` subelements

Element	Required	Description
ssl	only one	Defines SSL parameters.

### Attributes

none

## iiop-listener

Defines an IIOP listen socket.

To enable SSL for this listener, include an `ssl` subelement.

---

**NOTE** When you create a secure listener through the Administration interface, security is automatically turned on globally in `init.conf`. When you create a secure listener manually in `server.xml`, you must manually turn on security by editing the `init.conf` file's `Security` directive.

---

### Subelements

The following table describes subelements for the `iiop-listener` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-24** `iiop-listener` subelements

Element	Required	Description
<code>ssl</code>	zero or one	Defines SSL parameters.
<code>property</code>	zero or more	Specifies a property or a variable.

### Attributes

The following table describes attributes for the `iiop-listener` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-25** `iiop-listener` attributes

Attribute	Default	Description
<code>id</code>	none	The listener name. An <code>iiop-listener</code> name cannot begin with a number.
<code>address</code>	none	IP address of the listener. Can be in dotted-pair or IPv6 notation or just a name.
<code>port</code>	3700 (for the first server instance)	(optional) Port number to create the listener on. Legal values are 1 - 65535. On UNIX, creating sockets that listen on ports 1 - 1024 requires superuser privileges.

**Table 2-25** `iiop-listener` attributes

Attribute	Default	Description
<code>enabled</code>	<code>true</code>	(optional) Determines whether the listener is active. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .

## Container Elements

Container configuration elements are as follows:

- `web-container`
- `ejb-container`
- `mdb-container`

### **web-container**

Configures the web container.

#### **Subelements**

The following table describes subelements for the `web-container` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-26** `web-container` subelements

Element	Required	Description
<code>property</code>	zero or more	Specifies a property or a variable.

#### **Attributes**

The following table describes attributes for the `web-container` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-27** `web-container` attributes

Attribute	Default	Description
<code>monitoring-enabled</code>	<code>false</code>	(optional) Determines whether monitoring of the web container is enabled. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .

**Table 2-27** web-container attributes

Attribute	Default	Description
log-level	Value of level attribute of log-service element	(optional) Controls the type of messages logged by this element to the server log. For details, see the description of the level attribute of the log-service element. <code>ServletContext.log</code> messages are logged at the <code>INFO</code> level by default.

## ejb-container

Configures the EJB container. Stateless session beans are maintained in pools. Stateful session beans have session affinity and are cached. Entity beans associated with a database primary key are also cached. Entity beans not yet associated with a primary key are maintained in pools. Pooled entity beans are used to run `ejbCreate()` and finder methods.

### Subelements

The following table describes subelements for the `ejb-container` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-28** ejb-container subelements

Element	Required	Description
property	zero or more	Specifies a property or a variable.

### Attributes

The following table describes attributes for the `ejb-container` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-29** `ejb-container` attributes

Attribute	Default	Description
<code>steady-pool-size</code>	32	<p>(optional) Specifies the initial and minimum number of beans maintained in the pool. Must be 0 or greater and less than <code>max-pool-size</code>.</p> <p>Bean instances are removed from the pool and returned after use. The pool is replenished or cleaned up periodically to maintain this size.</p> <p>Applies to stateless session beans and entity beans.</p>
<code>pool-resize-quantity</code>	16	<p>(optional) Specifies the number of beans to be:</p> <ul style="list-style-type: none"> <li>• created if a request arrives when the pool has no available beans (subject to the <code>max-pool-size</code> limit)</li> <li>• removed when the <code>pool-idle-timeout-in-seconds</code> timer expires and a cleaner thread removes any unused instances</li> </ul> <p>Must be 0 or greater and less than <code>max-pool-size</code>. The pool is not resized below the <code>steady-pool-size</code>.</p> <p>Applies to stateless session beans and entity beans.</p>
<code>max-pool-size</code>	64	<p>(optional) Specifies the maximum number of beans that can be created to satisfy client requests. A value of 0 indicates an unbounded pool.</p> <p>Applies to stateless session beans and entity beans.</p>

**Table 2-29** `ejb-container` attributes

Attribute	Default	Description
<code>cache-resize-quantity</code>	16	<p>(optional) Specifies the number of beans to be:</p> <ul style="list-style-type: none"> <li>created if a request arrives when the pool has no available beans (subject to the <code>max-cache-size</code> limit)</li> <li>passivated when the <code>cache-idle-timeout-in-seconds</code> timer expires and a cleaner thread removes any unused instances, or when the cache size exceeds <code>max-cache-size</code>.</li> </ul> <p>Must be greater than 1 and less than <code>max-cache-size</code>.</p> <p>Applies to stateful session beans and entity beans.</p>
<code>max-cache-size</code>	512	<p>(optional) Specifies the maximum number of beans in the cache. A value of 0 indicates an unbounded cache.</p> <p>Applies to stateful session beans and entity beans.</p>
<code>pool-idle-timeout-in-seconds</code>	600	<p>(optional) Specifies the maximum time that a bean can remain idle in the pool. After this amount of time, the pool can remove this bean. A value of 0 specifies that idle beans can remain in the pool indefinitely.</p> <p>Applies to stateless session beans and entity beans.</p>
<code>cache-idle-timeout-in-seconds</code>	600	<p>(optional) Specifies the maximum time that a bean can remain idle in the cache. After this amount of time, the container can passivate this bean. A value of 0 specifies that beans may never become candidates for passivation.</p> <p>Applies to stateful session beans and entity beans.</p>

**Table 2-29** `ejb-container` attributes

Attribute	Default	Description
<code>removal-timeout-in-seconds</code>	5400	<p>(optional) Specifies the amount of time that a bean can remain passivated before it is removed from the session store. A value of 0 specifies that the container does not remove inactive beans automatically.</p> <p>If <code>removal-timeout-in-seconds</code> is less than or equal to <code>cache-idle-timeout-in-seconds</code>, beans are removed immediately without being passivated.</p> <p>The <code>session-store</code> attribute of the <code>server</code> element determines the location of the session store.</p> <p>Applies to stateful session beans and entity beans.</p>
<code>victim-selection-policy</code>	<code>nru</code>	<p>(optional) Specifies how entity and stateful session beans are selected for passivation. Allowed values are <code>fifo</code>, <code>lru</code>, and <code>nru</code>:</p> <ul style="list-style-type: none"> <li>• <code>fifo</code> selects the oldest instance.</li> <li>• <code>lru</code> selects the least recently accessed instance.</li> <li>• <code>nru</code> selects a not recently used instance.</li> </ul>
<code>commit-option</code>	<code>B</code>	<p>(optional) Determines which commit option is used for entity beans. Legal values are <code>B</code> or <code>C</code>.</p>
<code>log-level</code>	Value of <code>level</code> attribute of <code>log-service</code> element	<p>(optional) Controls the type of messages logged by this element to the server log. For details, see the description of the <code>level</code> attribute of the <code>log-service</code> element.</p>
<code>monitoring-enabled</code>	<code>false</code>	<p>(optional) Determines whether monitoring of the EJB container is enabled. Legal values are <code>on</code>, <code>off</code>, <code>yes</code>, <code>no</code>, <code>1</code>, <code>0</code>, <code>true</code>, <code>false</code>.</p>

## mdb-container

Configures the message-driven bean (MDB) container.

### Subelements

The following table describes subelements for the `mdb-container` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-30** `mdb-container` subelements

Element	Required	Description
<code>property</code>	zero or more	Specifies a property or a variable.

### Attributes

The following table describes attributes for the `mdb-container` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-31** `mdb-container` attributes

Attribute	Default	Description
<code>steady-pool-size</code>	10	(optional) Specifies the initial and minimum number of beans maintained in the pool.
<code>pool-resize-quantity</code>	2	(optional) Specifies the number of beans to be created if a request arrives when the pool is empty (subject to the <code>max-pool-size</code> limit), or the number of beans to remove if idle for more than <code>idle-timeout-in-seconds</code> .
<code>max-pool-size</code>	60	(optional) Specifies the maximum number of beans that can be created to satisfy client requests.
<code>idle-timeout-in-seconds</code>	600	(optional) Specifies the maximum time that a bean can remain idle in the pool. After this amount of time, the bean is destroyed.

**Table 2-31** mdb-container attributes

Attribute	Default	Description
log-level	Value of level attribute of log-service element	(optional) Controls the type of messages logged by this element to the server log. For details, see the description of the level attribute of the log-service element.
monitoring-enabled	false	(optional) Determines whether monitoring of the message-driven bean (MDB) container is enabled. Legal values are on, off, yes, no, 1, 0, true, false.

### Properties

The following table describes properties for the `mdb-container` element. The left column lists the property name, the middle column indicates the default value if the property is omitted, and the right column describes what the property does.

**Table 2-32** mdb-container properties

Property	Default	Description
cmt-max-runtime-exceptions	1	Specifies the maximum number of <code>RuntimeException</code> occurrences allowed from a message-driven bean's <code>onMessage()</code> method when container-managed transactions are used. Deprecated.
reconnect-enabled	true	If true, the MDB container automatically tries to reconnect to the JMS provider when the connection is broken.  When the connection is broken, depending on the message processing stage, the <code>onMessage()</code> method may not be able to complete successfully or the transaction may be rolled back due to a JMS exception. When the MDB container reestablishes the connection, JMS message redelivery semantics apply.
reconnect-delay-in-seconds	60	Specifies the delay between reconnect attempts.
reconnect-max-retries	60	Specifies the maximum number of reconnect attempts.

# J2EE Service Elements

J2EE service elements are as follows:

- `jms-service`
- `log-service`
- `security-service`
- `auth-realm`
- `transaction-service`

## **jms-service**

Configures the built-in Java Message Service (JMS) that is managed by the Sun ONE Application Server.

### **Subelements**

The following table describes subelements for the `jms-service` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-33** `jms-service` subelements

Element	Required	Description
<code>property</code>	zero or more	Specifies a property or a variable.

### **Attributes**

The following table describes attributes for the `jms-service` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-34** `jms-service` attributes

Attribute	Default	Description
<code>port</code>	7676	(optional) Specifies the port number used by the JMS provider.
<code>admin-user-name</code>	admin	Specifies the administrator user name for the JMS provider.
<code>admin-password</code>	admin	Specifies the administrator password for the JMS provider.

**Table 2-34** `jms-service` attributes

Attribute	Default	Description
<code>init-timeout-in-seconds</code>	60	(optional) Specifies the amount of time the server instance waits at startup for the corresponding JMS instance to respond. If there is no response, startup is aborted. If set to 0, the server instance waits indefinitely.
<code>start-args</code>	none	(optional) Specifies the string of arguments supplied for startup of the corresponding JMS instance.
<code>log-level</code>	Value of <code>level</code> attribute of <code>log-service</code> element	(optional) Controls the type of messages logged by this element to the server log. For details, see the description of the <code>level</code> attribute of the <code>log-service</code> element.
<code>enabled</code>	true	(optional) If set to <code>true</code> , the Sun ONE Application Server instance is responsible for starting up and shutting down the JMS provider. If set to <code>false</code> , the Sun ONE Application Server instance does not start up nor shut down the JMS provider (either because the JMS provider is not used or because it is managed independently of the Sun ONE Application Server).  Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .

### Properties

The following table describes properties for the `jms-service` element. The left column lists the property name, the middle column indicates the default value if the property is omitted, and the right column describes what the property does.

**Table 2-35** `jms-service` properties

Property	Default	Description
<code>instance-name</code>	<i>domain_instance</i>	Specifies the full Sun ONE Message Queue broker instance name, which is a concatenation of the domain and server instance names. For example: <code>domain1_server1</code> .
<code>instance-name-suffix</code>	none	Specifies a suffix to add to the full Sun ONE Message Queue broker instance name. The suffix is separated from the instance name by an underscore character ( <code>_</code> ). For example, if the instance name is <code>domain1_server1</code> , appending the suffix <code>xyz</code> changes the instance name to <code>domain1_server1_xyz</code> .

**Table 2-35** `.jms-service` properties

Property	Default	Description
<code>append-version</code>	<code>false</code>	If <code>true</code> , appends the major and minor version numbers, preceded by underscore characters ( <code>_</code> ), to the full Sun ONE Message Queue broker instance name. For example, if the instance name is <code>domain1_server1</code> , appending the version numbers changes the instance name to <code>domain1_server1_7_0</code> .

## log-service

Configures the system logging service, which includes the following log files:

- The **server log** file stores messages from the default virtual server. Messages from other configured virtual servers also go here, unless the `log-file` attribute is explicitly specified in the `virtual-server-class` or `virtual-server` element. The default name is `server.log`.
- The **access log** file stores HTTP access messages from the default virtual server. The default name is `access.log`. To configure the access log, you use server application functions in the `init.conf` and `obj.conf` files. For more information, see the *Sun ONE Application Server Developer's Guide to NSAPI*.
- The **transaction log** files store transaction messages from the default virtual server. The default name of the directory for these files is `tx`.
- A **virtual server log** file stores messages from a `virtual-server-class` or `virtual-server` element that has an explicitly specified `log-file` attribute.

### Subelements

The following table describes subelements for the `log-service` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-36** `log-service` subelements

Element	Required	Description
<code>property</code>	zero or more	Specifies a property or a variable.

### Attributes

The following table describes attributes for the `log-service` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-37** `log-service` attributes

Attribute	Default	Description
<code>file</code>	<code>server.log</code> in the directory specified by the <code>log-root</code> attribute of the server element	(optional) Overrides the name or location of the server log. The file and directory in which the server log is kept must be writable by whatever user account the server runs as.  If you specify an absolute path, this value overrides the <code>log-root</code> attribute of the server element.  If you specify a relative path, it is relative to the <code>log-root</code> attribute of the server element. If no <code>log-root</code> value is specified, it is relative to <code>instance_dir/config</code> .
<code>level</code>	INFO	(optional) Controls the default type of messages logged by other elements to the server log. Many other elements can override this default in their <code>log-level</code> attributes. Allowed values are, from highest to lowest: <code>FINEST</code> , <code>FINER</code> , <code>FINE</code> , <code>CONFIG</code> , <code>INFO</code> , <code>WARNING</code> , <code>SEVERE</code> , <code>ALERT</code> , <code>FATAL</code> .  Each value logs all messages for all lower values; for example, <code>FINEST</code> logs all messages, and <code>FATAL</code> logs only <code>FATAL</code> messages. The default value is <code>SEVERE</code> , which logs all <code>SEVERE</code> , <code>ALERT</code> , and <code>FATAL</code> messages.
<code>log-stdout</code>	true	(optional) If true, redirects <code>stdout</code> output to the server log. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .
<code>log-stderr</code>	true	(optional) If true, redirects <code>stderr</code> output to the server log. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .
<code>echo-log-messages-to-stderr</code>	true	(optional) If true, sends log messages to <code>stderr</code> in addition to the server log. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .
<code>create-console</code>	false	(optional, Windows only) If true, creates a Windows console for <code>stderr</code> output. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .
<code>log-virtual-server-id</code>	false	(optional) If true, virtual server IDs are displayed in the virtual server logs. This is useful if multiple <code>virtual-server</code> elements share the same log file. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .

**Table 2-37** log-service attributes

Attribute	Default	Description
use-system-logging	false	(optional) If true, uses the UNIX syslog service or Windows Event Logging to produce and manage logs. Legal values are on, off, yes, no, 1, 0, true, false.

## security-service

Defines parameters and configuration information needed by the J2EE security service.

### Subelements

The following table describes subelements for the `security-service` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-38** security-service subelements

Element	Required	Description
auth-realm	one or more	Defines a realm for authentication.
property	zero or more	Specifies a property or a variable.

### Attributes

The following table describes attributes for the `security-service` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-39** security-service attributes

Attribute	Default	Description
default-realm	file	(optional) Specifies the active authentication realm (an <code>auth-realm</code> name attribute) for this server instance.
default-principal	none	(optional) Used as the identity of the default security context when necessary and when no principal is provided. This attribute need not be set for normal server operation.

**Table 2-39** security-service attributes

Attribute	Default	Description
default-principal-password	none	(optional) The password of the default principal. This attribute need not be set for normal server operation.
anonymous-role	ANYONE	(optional) Used as the name for default, or anonymous, role. The anonymous role is always assigned to all principals. This role value can be used in J2EE deployment descriptors to grant access to anyone.
audit-enabled	false	(optional) If true, additional access logging is performed to provide audit information. Legal values are on, off, yes, no, 1, 0, true, false.  Audit information consists of: <ul style="list-style-type: none"> <li>• Authentication success and failure events</li> <li>• Servlet and EJB access grants and denials</li> </ul>
log-level	Value of level attribute of log-service element	(optional) Controls the type of messages logged by this element to the server log. For details, see the description of the level attribute of the log-service element.

## auth-realm

Defines a realm for authentication.

Authentication realms require provider-specific properties, which vary depending on what a particular implementation needs.

For more information about how to define realms, see the *Sun ONE Application Server Developer's Guide*.

Here is an example of the default file realm:

```
<auth-realm name="file"
  classname="com.ipplanet.ias.security.auth.realm.file.FileRealm">
  <property name="file" value="instance_dir/config/keyfile"/>
  <property name="jaas-context" value="fileRealm"/>
</auth-realm>
```

Which properties an `auth-realm` element uses depends on the value of the `auth-realm` element's `name` attribute. The `file` realm uses `file` and `jaas-context` properties. Other realms use different properties.

### Subelements

The following table describes subelements for the `auth-realm` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-40** `auth-realm` subelements

Element	Required	Description
<code>property</code>	zero or more	Specifies a property or a variable.

### Attributes

The following table describes attributes for the `auth-realm` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-41** `auth-realm` attributes

Attribute	Default	Description
<code>name</code>	<code>none</code>	Specifies the name of this realm.
<code>classname</code>	<code>none</code>	Specifies the Java class that implements this realm.

### Properties

The standard realms provided with Sun ONE Application Server have required and optional properties. A custom realm may have different properties.

The following table describes properties for the `auth-realm` element. The left column lists the property name, the middle column indicates the standard realms that use the property, and the right column describes what the property does.

**Table 2-42** `auth-realm` properties

Property	Realms	Description
<code>jaas-context</code>	<code>file</code> , <code>ldap</code> , <code>solaris</code>	Specifies the JAAS (Java Authentication and Authorization Service) context.

**Table 2-42** auth-realm properties

Property	Realms	Description
file	file	Specifies the file that stores user names. The default is <i>instance_dir</i> /config/keyfile.
assign-groups	certificate	(optional) If this property is set, its value is taken to be a comma-separated list of group names. All clients who present valid certificates are assigned membership to these groups for the purposes of authorization decisions in the web and EJB containers.
directory	ldap	Specifies the LDAP URL to your server.
base-dn	ldap	Specifies the LDAP base DN for the location of user data. This base DN can be at any level above the user data, since a tree scope search is performed. The smaller the search tree, the better the performance.
search-filter	ldap	(optional) Specifies the search filter to use to find the user. The default is uid=%s (%s expands to the subject name).
group-base-dn	ldap	(optional) Specifies the base DN for the location of groups data. By default it is same as the base-dn, but it can be tuned if necessary.
group-search-filter	ldap	(optional) Specifies the search filter to find group memberships for the user. The default is uniquemember=%d (%d expands to the user element DN).
group-target	ldap	(optional) Specifies the LDAP attribute name that contains group name entries. The default is CN.
search-bind-dn	ldap	(optional) Specifies an optional DN used to authenticate to the directory for performing the search-filter lookup. Only required for directories that do not allow anonymous search.
search-bind-password	ldap	(optional) Specifies the LDAP password for the DN given in search-bind-dn.

## transaction-service

Configures the Java Transaction Service (JTS).

### Subelements

The following table describes subelements for the `transaction-service` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-43** transaction-service subelements

Element	Required	Description
property	zero or more	Specifies a property or a variable.

**Attributes**

The following table describes attributes for the `transaction-service` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-44** transaction-service attributes

Attribute	Default	Description
automatic-recovery	false	(optional) If <code>true</code> , the server instance attempts transaction recovery during startup. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .
timeout-in-seconds	0	(optional) Specifies the amount of time after which the transaction is aborted. If set to 0, the transaction never times out.
tx-log-dir	directory specified by the <code>log-root</code> attribute of the server element	(optional) Overrides the location of the transaction log directory. The directory in which the transaction logs are kept must be writable by whatever user account the server runs as. See the <code>log-service</code> description for details about logs.
heuristic-decision	rollback	(optional) During recovery, if the outcome of a transaction cannot be determined from the logs, this property determines the outcome. Allowed values are <code>rollback</code> and <code>commit</code> .
keypoint-interval	2048	(optional) Specifies the number of transactions between keypoint operations in the log. Keypoint operations reduce the size of the transaction log file by compressing it. A larger value for this attribute (for example, 4096) results in a larger transaction log file, but fewer keypoint operations and potentially better performance. A smaller value (for example, 100) results in smaller log files, but slightly reduced performance due to the greater frequency of keypoint operations.
log-level	Value of <code>level</code> attribute of <code>log-service</code> element	(optional) Controls the type of messages logged by this element to the server log. For details, see the description of the <code>level</code> attribute of the <code>log-service</code> element.

**Table 2-44** transaction-service attributes

Attribute	Default	Description
monitoring-enabled	false	(optional) Determines whether monitoring of the JTS is enabled. Legal values are on, off, yes, no, 1, 0, true, false. The default is false.

**Properties**

The following table describes properties for the `transaction-service` element. The left column lists the property name, the middle column indicates the default value if the property is omitted, and the right column describes what the property does.

**Table 2-45** transaction-service properties

Property	Default	Description
oracle-xa-recovery-workaround	false	If true, the Oracle XA Resource workaround is used in transaction recovery. Legal values are on, off, yes, no, 1, 0, true, false.
sybase-xa-recovery-workaround	false	If true, the Sybase XA Resource workaround is used in transaction recovery. Legal values are on, off, yes, no, 1, 0, true, false.
disable-distributed-transaction-logging	false	If true, disables transaction logging, which may improve performance. Legal values are on, off, yes, no, 1, 0, true, false.  If the <code>automatic-recovery</code> attribute is set to true, this property is ignored.
xaresource-txn-timeout	specific to the XAResource used	Changes the XAResource timeout. In some cases, the XAResource default timeout can cause transactions to be aborted, so it is desirable to change it.

## Java Configuration Elements

Java configuration elements are as follows:

- `java-config`
- `profiler`
- `jvm-options`

## java-config

Specifies Java Virtual Machine (JVM) configuration parameters.

### Subelements

The following table describes subelements for the `java-config` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-46** `java-config` subelements

Element	Required	Description
<code>profiler</code>	zero or one	Configures a profiler for use with Sun ONE Application Server.
<code>jvm-options</code>	zero or more	Contains JVM command line options.
<code>property</code>	zero or more	Specifies a property or a variable.

### Attributes

The following table describes attributes for the `java-config` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-47** `java-config` attributes

Attribute	Default	Description
<code>java-home</code>	none	The path to the directory where the JDK is installed.
<code>debug-enabled</code>	false	(optional) If <code>true</code> , the server starts up in debug mode ready for attachment with a JPDA-based debugger. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .
<code>debug-options</code>	<code>-Xdebug</code> <code>-Xrunjdwp:transport=dt_socket,server=y,suspend=n</code>	(optional) Specifies JPDA (Java Platform Debugger Architecture) options. A list of debugging options that you can include is available here:  <a href="http://java.sun.com/products/jpda/doc/conninv.html#Invocation">http://java.sun.com/products/jpda/doc/conninv.html#Invocation</a>  For more information about debugging, see the <i>Sun ONE Application Server Developer's Guide</i> .

**Table 2-47** java-config attributes

Attribute	Default	Description
rmic-options	-iio -poa -alwaysgenerate -keepgenerated -g	(optional) Specifies options passed to the RMI compiler at application deployment time. The <code>-keepgenerated</code> option saves generated source for stubs and ties.  For more information about the <code>rmic</code> command, see the <i>Sun ONE Application Server Developer's Guide to Enterprise JavaBeans Technology</i> .
javac-options	-g	(optional) Specifies options passed to the Java compiler at application deployment time.
classpath-prefix	none	(optional) Specifies a prefix for the system classpath. You should only prefix the system classpath if you wish to override system classes, such as the XML parser classes. Use this attribute with caution.
server-classpath	none	(optional) Specifies the classpath for the environment from which the server was started. This classpath can be accessed using <code>System.getProperty("java.class.path")</code> .
classpath-suffix	none	(optional) Specifies a suffix for the system classpath.
native-library-path-prefix	none	(optional) Specifies a prefix for the native library path.  The native library path is the automatically constructed concatenation of the Sun ONE Application Server installation relative path for its native shared libraries, the standard JRE native library path, the shell environment setting ( <code>LD_LIBRARY_PATH</code> on UNIX), and any path specified in the <code>profiler</code> element. Since this is synthesized, it does not appear explicitly in the server configuration.
native-library-path-suffix	none	(optional) Specifies a suffix for the native library path.

**Table 2-47** `java-config` attributes

Attribute	Default	Description
<code>bytecode-preprocessors</code>		(optional) A comma separated list of class names, each of which must implement the <code>com.sun.appserv.BytecodePreprocessor</code> or interface. Each of the specified preprocessor classes is called in the order specified.
<code>env-classpath-ignored</code>	<code>true</code>	(optional) If <code>false</code> , the <code>CLASSPATH</code> environment variable is read and appended to the Sun ONE Application Server classpath. The <code>CLASSPATH</code> environment variable is added after the <code>classpath-suffix</code> , at the very end.  For a development environment, this value should be set to <code>false</code> . For a production environment, this value should be set to <code>true</code> to prevent environment variable side effects.  Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .

## profiler

Configures a profiler for use with Sun ONE Application Server. For more information about profilers, see the *Sun ONE Application Server Developer's Guide*.

### Subelements

The following table describes subelements for the `profiler` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-48** `profiler` subelements

Element	Required	Description
<code>jvm-options</code>	zero or more	Contains profiler-specific JVM command line options.
<code>property</code>	zero or more	Specifies a property or a variable.

**NOTE** Subelements of a `profiler` element can occur in any order.

**Attributes**

The following table describes attributes for the `profiler` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-49** `profiler` attributes

Attribute	Default	Description
<code>name</code>	<code>none</code>	Specifies the name of the profiler.
<code>classpath</code>	<code>none</code>	(optional) Specifies the classpath for the profiler.
<code>native-library-path</code>	<code>none</code>	(optional) Specifies the native library path for the profiler.
<code>enabled</code>	<code>true</code>	(optional) Determines whether the profiler is enabled. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .

**jvm-options**

Contains JVM command line options, for example:

```
<jvm-options>-Xdebug -Xmx128m</jvm-options>
```

For information about the options you can use, see:

<http://java.sun.com/docs/hotspot/VMOptions.html>

**Subelements**

`none`

**Attributes**

`none`

## Resource Elements

Resource elements are as follows:

- `resources`
- `custom-resource`
- `external-jndi-resource`

- `jdbc-resource`
- `mail-resource`
- `jms-resource`
- `persistence-manager-factory-resource`
- `jdbc-connection-pool`

## resources

Contains configured resources, such as database connections, JavaMail sessions, and so on.

---

**NOTE** You must specify a JNDI name for each resource. To avoid collisions with names of other enterprise resources in JNDI, and to avoid portability problems, all names in a Sun ONE Application Server application should begin with the string `java:comp/env`.

---

### Subelements

The following table describes subelements for the `resources` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-50** `resources` subelements

Element	Required	Description
<code>custom-resource</code>	zero or more	Defines a custom resource.
<code>external-jndi-resource</code>	zero or more	Defines a resource that resides in an external JNDI repository.
<code>jdbc-resource</code>	zero or more	Defines a JDBC (Java Database Connectivity) resource.
<code>mail-resource</code>	zero or more	Defines a JavaMail resource.
<code>jms-resource</code>	zero or more	Defines a JMS resource.
<code>persistence-manager-factory-resource</code>	zero or more	Defines a persistence manager factory resource for CMP.
<code>jdbc-connection-pool</code>	zero or more	Defines the properties that are required for creating a JDBC connection pool.

---

**NOTE** Subelements of a `resources` element can occur in any order.

---

### Attributes

none

## custom-resource

Defines a custom resource, which specifies a custom server-wide resource object factory. Such object factories implement the `javax.naming.spi.ObjectFactory` interface.

### Subelements

The following table describes subelements for the `custom-resource` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-51** `custom-resource` subelements

Element	Required	Description
<code>description</code>	zero or one	Contains a text description of this element.
<code>property</code>	zero or more	Specifies a property or a variable.

### Attributes

The following table describes attributes for the `custom-resource` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-52** `custom-resource` attributes

Attribute	Default	Description
<code>jndi-name</code>	none	Specifies the JNDI name for the resource.
<code>res-type</code>	none	Specifies the fully qualified type of the resource.
<code>factory-class</code>	none	Specifies the fully qualified name of the user-written factory class, which implements <code>javax.naming.spi.ObjectFactory</code> .
<code>enabled</code>	true	(optional) Determines whether this resource is enabled at runtime. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .

## external-jndi-resource

Defines a resource that resides in an external JNDI repository. For example, a generic Java object could be stored in an LDAP server. An external JNDI factory must implement the `javax.naming.spi.InitialContextFactory` interface.

### Subelements

The following table describes subelements for the `external-jndi-resource` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-53** `external-jndi-resource` subelements

Element	Required	Description
<code>description</code>	zero or one	Contains a text description of this element.
<code>property</code>	zero or more	Specifies a property or a variable.

### Attributes

The following table describes attributes for the `external-jndi-resource` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-54** `external-jndi-resource` attributes

Attribute	Default	Description
<code>jndi-name</code>	none	Specifies the JNDI name for the resource.
<code>jndi-lookup-name</code>	none	Specifies the JNDI lookup name for the resource.
<code>res-type</code>	none	Specifies the fully qualified type of the resource.
<code>factory-class</code>	none	Specifies the fully qualified name of the factory class, which implements <code>javax.naming.spi.InitialContextFactory</code> .  For more information about JNDI, see the <i>Sun ONE Application Server Developer's Guide to J2EE Features and Services</i> .
<code>enabled</code>	true	(optional) Determines whether this resource is enabled at runtime. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .

## jdbc-resource

Defines a JDBC (`javax.sql.DataSource`) resource.

### Subelements

The following table describes subelements for the `jdbc-resource` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-55** `jdbc-resource` subelements

Element	Required	Description
<code>description</code>	zero or one	Contains a text description of this element.
<code>property</code>	zero or more	Specifies a property or a variable.

### Attributes

The following table describes attributes for the `jdbc-resource` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-56** `jdbc-resource` attributes

Attribute	Default	Description
<code>jndi-name</code>	none	Specifies the JNDI name for the resource.
<code>pool-name</code>	none	Specifies the name of the associated JDBC connection pool, defined in a <code>jdbc-connection-pool</code> element.
<code>enabled</code>	true	(optional) Determines whether this resource is enabled at runtime. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .

## mail-resource

Defines a JavaMail (`javax.mail.Session`) resource.

### Subelements

The following table describes subelements for the `mail-resource` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-57** mail-resource subelements

Element	Required	Description
description	zero or one	Contains a text description of this element.
property	zero or more	Specifies a property or a variable.

**Attributes**

The following table describes attributes for the mail-resource element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-58** mail-resource attributes

Attribute	Default	Description
jndi-name	none	Specifies the JNDI name for the resource.
store-protocol	imap	(optional) Specifies the storage protocol service, which connects to a mail server, retrieves messages, and saves messages in folder(s). Example values are <code>imap</code> and <code>pop3</code> .
store-protocol-class	<code>com.sun.mail.imap.IMAPStore</code>	(optional) Specifies the service provider implementation class for storage.
transport-protocol	smtp	(optional) Specifies the transport protocol service, which sends messages.
transport-protocol-class	<code>com.sun.mail.smtp.SMTPTransport</code>	(optional) Specifies the service provider implementation class for transport.
host	none	The mail server host name.
user	none	The mail server user name.
from	none	The e-mail address the mail server uses to indicate the message sender.
debug	false	(optional) Determines whether debugging for this resource is enabled. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .
enabled	true	(optional) Determines whether this resource is enabled at runtime. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .

### Properties

You can set properties for the `mail-resource` element and then get these properties in a JavaMail `Session` object later. Every property name must start with a `mail-` prefix. Sun ONE Application Server changes the dash (-) character to a period (.) in the name of the property and saves the property to the `MailConfiguration` and JavaMail `Session` objects. If the name of the property doesn't start with `mail-`, the property is ignored.

For example, if you want to define the property `mail.password` in a JavaMail `Session` object, first edit `server.xml` as follows:

```
...
<mail-resource jndi-name="mail/Session" ...>
  <property name="mail-password" value="adminadmin"/>
</mail-resource>
...
```

After you get the JavaMail `Session` object, you can get the `mail.password` property to retrieve the value `adminadmin`, as follows:

```
String password = session.getProperty("mail.password");
```

## jms-resource

Defines a JMS (Java Message Service) resource.

### Subelements

The following table describes subelements for the `jms-resource` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-59** `jms-resource` subelements

Element	Required	Description
<code>description</code>	zero or one	Contains a text description of this element.
<code>property</code>	zero or more	Specifies a property or a variable.

### Attributes

The following table describes attributes for the `jms-resource` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-60** `jms-resource` attributes

Attribute	Default	Description
<code>jndi-name</code>	none	Specifies the JNDI name for the resource.
<code>res-type</code>	none	Specifies the fully qualified type of the resource, which is one of the following:  <code>javax.jms.Topic</code> <code>javax.jms.Queue</code> <code>javax.jms.TopicConnectionFactory</code> <code>javax.jms.QueueConnectionFactory</code>
<code>enabled</code>	true	(optional) Determines whether this resource is enabled at runtime. Legal values are on, off, yes, no, 1, 0, true, false.

### Properties

The following table describes properties for the `jms-resource` element. The left column lists the property name, the middle column indicates the default value if the property is omitted, and the right column describes what the property does.

**Table 2-61** `jms-resource` properties

Property	Default	Description
<code>imqDestinationName</code>	none	Specifies the JMS physical destination name associated with this JMS resource. You must specify this property for <code>jms-resource</code> elements with the <code>res-type</code> of <code>javax.jms.Topic</code> or <code>javax.jms.Queue</code> .  The <i>Sun ONE Message Queue Administrator's Guide</i> shows a default value for this property, but this does not apply in the Sun ONE Application Server environment.
<code>imqBrokerHostName</code>	the same host name as the Sun ONE Application Server instance (localhost)	Specifies the host name where the JMS service (Sun ONE Message Queue broker) is running. For <code>jms-resource</code> elements with the <code>res-type</code> of <code>javax.jms.TopicConnectionFactory</code> or <code>javax.jms.QueueConnectionFactory</code> .
<code>imqBrokerHostPort</code>	the <code>jms-service</code> element's port attribute	Specifies the port where the JMS service (Sun ONE Message Queue broker) is running. For <code>jms-resource</code> elements with the <code>res-type</code> of <code>javax.jms.TopicConnectionFactory</code> or <code>javax.jms.QueueConnectionFactory</code> .

**Table 2-61** `.jms-resource` properties

Property	Default	Description
<code>imqConfiguredClientID</code>	<code>none</code>	<p>Specifies the JMS Client Identifier to be associated with a Connection created using the <code>createQueueConnection</code> and <code>createTopicConnection</code> JMS APIs of the <code>QueueConnectionFactory</code> and <code>TopicConnectionFactory</code> classes, respectively.</p> <p>For <code>.jms-resource</code> elements with the <code>res-type</code> of <code>javax.jms.TopicConnectionFactory</code> or <code>javax.jms.QueueConnectionFactory</code>.</p> <p>Durable subscription names are unique and only valid within the scope of a client identifier. To create or reactivate a durable subscriber, the connection must have a valid client identifier. The JMS specification ensures that client identifiers are unique and that a given client identifier is allowed to be used by only one active connection at a time.</p>

## **persistence-manager-factory-resource**

Defines a persistence manager factory resource for container-managed persistence (CMP).

### **Subelements**

The following table describes subelements for the `persistence-manager-factory-resource` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-62** `persistence-manager-factory-resource` subelements

Element	Required	Description
<code>description</code>	zero or one	Contains a text description of this element.
<code>property</code>	zero or more	Specifies a property or a variable.

### **Attributes**

The following table describes attributes for the `persistence-manager-factory-resource` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-63** persistence-manager-factory-resource attributes

Attribute	Default	Description
jndi-name	none	Specifies the JNDI name for the resource.
factory-class	com.sun.jdo.spi.persistence.support.sqlstore.impl.PersistenceManagerFactoryImpl	(optional) Specifies the name of the factory class. This attribute supports third party CMP persistence manager factories. Use the name required by the third party CMP implementation. Do not specify this attribute for the built-in CMP implementation.
jdbc-resource-jndi-name	none	(optional) Specifies the jdbc-resource from which database connections are obtained. Must be the jndi-name of an existing jdbc-resource.
enabled	true	(optional) Determines whether this resource is enabled at runtime. Legal values are on, off, yes, no, 1, 0, true, false.

## jdbc-connection-pool

Defines the properties that are required for creating a JDBC connection pool.

---

**TIP** You can create a pool definition and then copy, paste, and edit it to configure multiple JDBC data sources.

---

### Subelements

The following table describes subelements for the jdbc-connection-pool element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-64** jdbc-connection-pool subelements

Element	Required	Description
description	zero or one	Contains a text description of this element.
property	zero or more	Specifies a property or a variable.

**Attributes**

The following table describes attributes for the `jdbc-connection-pool` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-65** `jdbc-connection-pool` attributes

Attribute	Default	Description
<code>name</code>	none	Specifies the name of the connection pool. A <code>jdbc-resource</code> element's <code>pool-name</code> attribute refers to this name.
<code>datasource-classname</code>	none	Specifies the class name of the associated vendor-supplied data source. This class must implement <code>java.sql.DataSource</code> or <code>java.sql.XADataSource</code> or both.
<code>res-type</code>	<code>javax.sql.DataSource</code>	(optional) Specifies the interface the data source class implements. The value of this attribute can be <code>javax.sql.DataSource</code> or <code>javax.sql.XADataSource</code> . If the value is not one of these interfaces, the default is used. An error occurs if this attribute has a legal value and the indicated interface is not implemented by the data source class.
<code>steady-pool-size</code>	8	(optional) Specifies the initial and minimum number of connections maintained in the pool.
<code>max-pool-size</code>	32	(optional) Specifies the maximum number of connections that can be created to satisfy client requests.
<code>max-wait-time-in-millis</code>	60000	(optional) Specifies the amount of time, in milliseconds, that the caller is willing to wait for a connection. If 0, the caller is blocked indefinitely until a resource is available or an error occurs.
<code>pool-resize-quantity</code>	2	(optional) Specifies the number of connections to be destroyed if the existing number of connections is above the <code>steady-pool-size</code> (subject to the <code>max-pool-size</code> limit). This is enforced periodically at the <code>idle-time-out-in-seconds</code> interval. An idle connection is one that has not been used for a period of <code>idle-time-out-in-seconds</code> .

**Table 2-65** jdbc-connection-pool attributes

Attribute	Default	Description
idle-timeout-in-seconds	300	(optional) Specifies the maximum time that a connection can remain idle in the pool. After this amount of time, the pool can close this connection.
transaction-isolation-level	default JDBC driver isolation level	(optional) Specifies the transaction isolation level on the pooled database connections. Allowed values are <code>read-uncommitted</code> , <code>read-committed</code> , <code>repeatable-read</code> , or <code>serializable</code> .  Applications that change the isolation level on a pooled connection programmatically risk polluting the pool, which can lead to errors. See <code>is-isolation-level-guaranteed</code> for more details.
is-isolation-level-guaranteed	true	(optional) Applicable only when <code>transaction-isolation-level</code> is explicitly set. If <code>true</code> , every connection obtained from the pool is guaranteed to have the desired isolation level. This may impact performance on some JDBC drivers. You can set this attribute to <code>false</code> if you are certain that the hosted applications do not return connections with altered isolation levels.
is-connection-validation-required	false	(optional) Specifies whether connections have to be validated before being given to the application. If a resource's validation fails, it is destroyed, and a new resource is created and returned. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .
connection-validation-method	auto-commit	(optional) Legal values are as follows: <ul style="list-style-type: none"> <li>• <code>auto-commit</code> (default), which uses <code>Connection.setAutoCommit(Connection.getAutoCommit())</code></li> <li>• <code>meta-data</code>, which uses <code>Connection.getMetaData()</code></li> <li>• <code>table</code>, which performs a query on a table specified in the <code>validation-table-name</code> attribute</li> </ul>

**Table 2-65** jdbc-connection-pool attributes

Attribute	Default	Description
validation-table-name	none	(optional) Specifies the table name to be used to perform a query to validate a connection. This parameter is mandatory if and only if connection-validation-type is set to table.
fail-all-connections	false	(optional) If true, closes all connections in the pool if a single validation check fails. This parameter is mandatory if and only if is-connection-validation-required is set to true. Legal values are on, off, yes, no, 1, 0, true, false.

### Properties

Most JDBC 2.0 drivers allow use of standard property lists to specify the user, password, and other resource configuration information. Although properties are optional with respect to Sun ONE Application Server, some properties may be necessary for most databases. For details, see Section 5.3 of JDBC 2.0 Standard Extension API.

When properties are specified, they are passed to the vendor's data source class (specified by the `datasource-classname` attribute) as is using `setName(value)` methods.

The `user` and `password` properties are used as the default principal if container managed authentication is specified and a `default-resource-principal` is not found in the application deployment descriptors.

The following table describes some common properties for the `jdbc-connection-pool` element. The left column lists the property name, and the right column describes what the property does.

**Table 2-66** jdbc-connection-pool properties

Property	Description
<code>user</code>	Specifies the user name for this connection pool.
<code>password</code>	Specifies the password for this connection pool.
<code>databaseName</code>	Specifies the database for this connection pool.
<code>serverName</code>	Specifies the database server for this connection pool.
<code>port</code>	Specifies the port on which the database server listens for requests.

**Table 2-66** jdbc-connection-pool properties

Property	Description
networkProtocol	Specifies the communication protocol.
roleName	Specifies the initial SQL role name.
datasourceName	Specifies an underlying XADataSource, or a ConnectionPoolDataSource if connection pooling is done.
description	Specifies a text description.
url	Specifies the URL for this connection pool. Although this is not a standard property, it is commonly used.

## Application Elements

Application elements are as follows:

- applications
- lifecycle-module
- j2ee-application
- web-module
- ejb-module
- connector-module

### applications

Contains deployed J2EE applications, J2EE modules, and Lifecycle modules.

#### Subelements

The following table describes subelements for the `applications` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-67** applications subelements

Element	Required	Description
lifecycle-module	zero or more	Specifies a deployed lifecycle module.
j2ee-application	zero or more	Specifies a deployed J2EE application.
ejb-module	zero or more	Specifies a deployed EJB module.

**Table 2-67** applications subelements

Element	Required	Description
web-module	zero or more	Specifies a deployed web module.
connector-module	zero or more	Specifies a deployed connector module.

---

**NOTE** Subelements of an `applications` element can occur in any order.

---

### Attributes

The following table describes attributes for the `applications` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-68** applications attributes

Attribute	Default	Description
dynamic-reload -enabled	false	(optional) Specifies whether dynamic reloading is enabled. This attribute should be set to <code>true</code> in a development environment and <code>false</code> in a production environment. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .
dynamic-reload -poll-interval -in-seconds	2	(optional) Specifies the interval at which applications and modules are checked for code changes and dynamically reloaded.

## lifecycle-module

Specifies a deployed lifecycle module. For more information about lifecycle modules, see the *Sun ONE Application Server Developer's Guide*.

### Subelements

The following table describes subelements for the `lifecycle-module` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-69** lifecycle-module subelements

Element	Required	Description
description	zero or one	Contains a text description of this element.

**Table 2-69** `lifecycle-module` subelements

Element	Required	Description
<code>property</code>	zero or more	Specifies a property or a variable.

**Attributes**

The following table describes attributes for the `lifecycle-module` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-70** `lifecycle-module` attributes

Attribute	Default	Description
<code>name</code>	none	The name of the lifecycle module.
<code>class-name</code>	none	The fully qualified name of the lifecycle module's class file, which must implement the <code>com.sun.appserv.server.LifecycleListener</code> interface.
<code>classpath</code>	value of <code>application-root</code> attribute of <code>server</code> element	(optional) The classpath for the lifecycle module. Specifies where the module is located.
<code>load-order</code>	none	(optional) Determines the order in which lifecycle modules are loaded at startup. Modules with smaller integer values are loaded sooner. Values can range from 101 to the operating system's <code>MAXINT</code> . Values from 1 to 100 are reserved.
<code>is-failure-fatal</code>	false	(optional) Determines whether the server is shut down if the lifecycle module fails. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .
<code>enabled</code>	true	(optional) Determines whether the lifecycle module is enabled. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .

## j2ee-application

Specifies a deployed J2EE application.

**Subelements**

The following table describes subelements for the `j2ee-application` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-71** `j2ee-application` subelements

Element	Required	Description
<code>description</code>	zero or one	Contains a text description of this element.

**Attributes**

The following table describes attributes for the `j2ee-application` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-72** `j2ee-application` attributes

Attribute	Default	Description
<code>name</code>	none	The name of the application.
<code>location</code>	none	The location of the application in the Sun ONE Application Server file system.
<code>virtual-servers</code>	all virtual servers	(optional) The virtual servers to which the web modules within this application are deployed.
<code>enabled</code>	true	(optional) Determines whether the application is enabled. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .

**ejb-module**

Specifies a deployed EJB module.

**Subelements**

The following table describes subelements for the `ejb-module` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-73** `ejb-module` subelements

Element	Required	Description
<code>description</code>	zero or one	Contains a text description of this element.

**Attributes**

The following table describes attributes for the `ejb-module` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-74** `ejb-module` attributes

Attribute	Default	Description
<code>name</code>	<code>none</code>	The name of the EJB module.
<code>location</code>	<code>none</code>	The location of the EJB module in the Sun ONE Application Server file system.
<code>enabled</code>	<code>true</code>	(optional) Determines whether the EJB module is enabled. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .

**web-module**

Specifies a deployed web module.

**Subelements**

The following table describes subelements for the `web-module` element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-75** `web-module` subelements

Element	Required	Description
<code>description</code>	zero or one	Contains a text description of this element.

**Attributes**

The following table describes attributes for the `web-module` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-76** `web-module` attributes

Attribute	Default	Description
<code>name</code>	<code>none</code>	The name of the web module.

**Table 2-76** web-module attributes

Attribute	Default	Description
context-root	empty string	<p>The context root (context path without the / in front) at which the web module is installed (see Section 5.4 of the Servlet 2.3 specification).</p> <p>If this attribute is an empty string, which is the default value, this web module can be the default web module for the virtual-server elements specified in the virtual-servers attribute.</p> <p>If multiple web modules assigned to a virtual server have an empty context root, one of them is loaded, and the rest generate error messages such as: Virtual server [<i>virtual_server</i>] already has a web module loaded at [/].</p>
location	none	<p>A fully qualified or relative path to the directory to which the contents of the .war file have been extracted. If relative, it is relative to the following directory:</p> <p><i>instance_dir</i>/applications/j2ee-modules/</p>
virtual-servers	all virtual servers	(optional) The virtual-server elements to which the web module is deployed.
enabled	true	(optional) Determines whether the web module is enabled. Legal values are on, off, yes, no, 1, 0, true, false.

## connector-module

Specifies a deployed connector module.

### Subelements

The following table describes subelements for the connector-module element. The left column lists the subelement name, the middle column indicates the requirement rule, and the right column describes what the element does.

**Table 2-77** connector-module subelements

Element	Required	Description
description	zero or one	Contains a text description of this element.

**Attributes**

The following table describes attributes for the `connector-module` element. The left column lists the attribute name, the middle column indicates the default value, and the right column describes what the attribute does.

**Table 2-78** `connector-module` attributes

Attribute	Default	Description
<code>name</code>	<code>none</code>	The name of the connector module.
<code>location</code>	<code>none</code>	The location of the connector module in the Sun ONE Application Server file system.
<code>enabled</code>	<code>true</code>	(optional) Determines whether the connector module is enabled. Legal values are <code>on</code> , <code>off</code> , <code>yes</code> , <code>no</code> , <code>1</code> , <code>0</code> , <code>true</code> , <code>false</code> .

## User Database Selection

---

**NOTE** The user database applies only to the security of the server itself. It is not related to J2EE application and module security.

---

The `auth-db` element in `server.xml` selects a user database for the parent `virtual-server` element as follows:

- The `auth-db` element's `id` attribute maps to an ACL file's `database` attribute.
- The `auth-db` element's `database` attribute maps to a `dbswitch.conf` entry.

This layer between the ACL file and the `dbswitch.conf` file gives the server administrator full control over which databases virtual server administrators and users have access to.

---

**NOTE** The `dbswitch.conf` interface is Unstable. An unstable interface may be experimental or transitional, and hence may change incompatibly, be removed, or be replaced by a more stable interface in the next release.

---

The `dbswitch.conf` file establishes the root of the search tree for LDAP databases as follows:

- The base DN in the LDAP URL in `dbswitch.conf` defines a root object for all further DN specifications. So, for most new installations, it can be empty, because the final base DN is determined in other ways -- either through a DC tree lookup or an explicit `basedn` value in the `auth-db` element.
- A `dbswitch.conf` attribute for LDAP databases, `dcsuffix`, defines the root of the DC tree. This root is relative to the base DN in the LDAP URL. You can use `dcsuffix` if the database is *schema compliant*. Requirements for schema compliance are listed in “The Sun ONE LDAP Schema” on page 88.

A user database is selected for a virtual server as follows:

- If a `virtual-server` has no `auth-db` subelement, user- or group-based ACLs fail.
- When no `database` attribute is present in a virtual server’s ACL definition, the `virtual-server` must have an `auth-db` subelement with an `id` attribute of `default`. The `database` attribute of the `auth-db` then points to a database in `dbswitch.conf`. If no `database` attribute is present, `default` is used.
- If an LDAP database is schema compliant, the base DN of the access is computed using a DC tree lookup of the `virtual-server` element’s `hosts` attribute that matches the client-supplied `Host` header. If no `hosts` attribute matches, the `server-name` attribute of the parent `http-listener` is used. The DC tree lookup is based at the `dcsuffix` DN. The result must contain an `inetDomainBaseDN` attribute that contains the base DN. This base DN is taken as is and is not relative to any of the base DN values.
- If the `basedn` attribute of the `auth-db` element is not present and the database is not schema compliant, the accesses happen relative to the base DN in the `dbswitch.conf` entry, as in previous Sun ONE Application Server versions.

## The Sun ONE LDAP Schema

You can use the `dcsuffix` attribute in the `dbswitch.conf` file if your LDAP database meets the requirements outlined in this section.

The subtree rooted at an ISP entry (for example, `o=isp`) is called the *convergence tree*. It contains all the directory data related to organizations (customers) served by an ISP.

The subtree rooted at `o=internet` is called the *domain component tree* or *dc tree*. It contains a sparse DNS tree with entries for the customer domains served. These entries are links to the appropriate location in the convergence tree where the data for that domain is located.

The directory tree may be single rooted, which is recommended (for example, `o=root` may have `o=isp` and `o=internet` under it), or have two separate roots, one for the convergence tree and one for the dc tree.

## The Convergence Tree

The top level of the convergence tree must have one organization entry for each customer (or organization), and one for the ISP itself.

Underneath each organization, there must be two `organizationalUnit` entries: `ou=People` and `ou=Groups`. A third, `ou=Devices`, can be present if device data is to be stored for the organization.

Each user entry must have a unique `uid` value within a given organization. The namespace under this subtree can be partitioned into various `ou` entries that aggregate user entries in convenient groups (for example, `ou=eng`, `ou=corp`). User `uid` values must still be unique within the entire `People` subtree.

User entries in the convergence tree are of type `inetOrgPerson`. The `cn`, `sn`, and `uid` attributes must be present. The `uid` attribute must be a valid e-mail name (specifically, it must be a valid local-part as defined in RFC822). It is recommended that the `cn` contain *name initial sn*. It is recommended that the RDN of the user entry be the `uid` value. User entries must contain the auxiliary class `inetUser` if they are to be considered enabled for service or valid.

User entries can also contain the auxiliary class `inetSubscriber`, which is used for account management purposes. If an `inetUserStatus` attribute is present in an entry and has a value of `inactive` or `deleted`, the entry is ignored.

Groups are located under the `Groups` subtree and consist of LDAP entries of type `groupOfUniqueNames`.

## The Domain Component (dc)Tree

The dc tree contains hierarchical `domain` entries, each of which is a DNS name component.

Entries that represent the domain name of a customer are overlaid with the LDAP auxiliary class `inetDomain`. For example, the two LDAP entries `dc=customer1,dc=com,o=Internet,o=root` and `dc=customer2,dc=com,o=Internet,o=root` contain the `inetDomain` class, but `dc=com,o=Internet,o=root` does not. The latter is present only to provide structure to the tree.

Entries with an `inetDomain` attribute are called virtual domains. These must have the attribute `inetDomainBaseDN` filled with the DN of the top level organization entry where the data of this domain is stored in the convergence tree. For example, the virtual domain entry in `dc=cust2,dc=com,o=Internet,o=root` would contain the attribute `inetDomainBaseDN` with value `o=Cust2,o=isp,o=root`.

If an `inetDomainStatus` attribute is present in an entry and has a value of `inactive` or `deleted`, the entry is ignored.

## Variables

Some variables are defined in `server.xml` for use in the `obj.conf` file. The following file fragment defines a `docroot` variable:

```
<property name="docroot" value="/server/docs/class2/acme" />
```

A `docroot` variable allows different document root directories to be assigned for different virtual servers. The variable is then used in the `obj.conf` file. For example:

```
NameTrans fn=document-root root="$docroot"
```

Using this `docroot` variable allows you to define different document roots for different virtual servers within the same virtual server class.

---

**NOTE** A variable must be defined in the `server.xml` file at the `http-service`, `virtual-server-class`, or `virtual-server` level. Defining variables with default values at the `http-service` or `virtual-server-class` level and overriding them at the `virtual-server` level is recommended.

---

## Format of a Variable

A variable is found in `obj.conf` when the following regular expression matches:

```
\${[A-Za-z][A-Za-z0-9_]*}
```

This expression represents a `$` followed by one or more alphanumeric characters. A delimited version ("`{property}`") is not supported. To get a regular `$` character, use `$$` to have variable substitution.

## The id Variable

A special variable, `id`, is always available within a `virtual-server` element and refers to the value of the `id` attribute. It is predefined and cannot be overridden. The `id` attribute uniquely identifies a virtual server. For example:

```
<property name=docroot value="/export/$id" />
```

If the `id` attribute of the parent `virtual-server` element is `myserver`, the `docroot` variable is set to the value `/export/myserver`.

## Other Important Variables

The following variables are used in various parts of the Sun ONE Application Server configuration. Unlike the `$id` variable, they are not predefined in the server, and they can be overridden.

### General Variables

The following table lists general `server.xml` variables. The left column lists variables, and the right column lists descriptions of those variables.

**Table 2-79** General variables

Variable	Description
<code>docroot</code>	The document root of the virtual server. Typically evaluated as the parameter to the <code>document-root</code> function in the <code>obj.conf</code> file.
<code>accesslog</code>	The access log file for a virtual server.

### send-cgi Variables

The following table lists `server.xml` variables used by the `send-cgi` function in the `obj.conf` file. The left column lists variables, and the right column lists descriptions of those variables.

**Table 2-80** send-cgi variables

Variable	Description
<code>user</code>	The value of the <code>user</code> CGI parameter.
<code>group</code>	The value of the <code>group</code> CGI parameter.

**Table 2-80** send-cgi variables

Variable	Description
chroot	The value of the <code>chroot</code> CGI parameter.
dir	The value of the <code>dir</code> CGI parameter.
nice	The value of the <code>nice</code> CGI parameter.

For more information about the `send-cgi` function, see the *Sun ONE Application Server Developer's Guide to NSAPI*.

## Variable Evaluation

Variables are evaluated when generating specific objects for individual virtual servers. Evaluation is recursive: variable values can contain other variables. For example:

```
...
<virtual-server-class>
  ...
  <virtual-server ...>
    ...
    <property name=docroot value="$docrootbase/nonjava/$id" />
  </virtual-server>
  <virtual-server ...>
    ...
    <property name=docroot value="$docrootbase/java/$id" />
  </virtual-server>
  ...
  <property name=docrootbase value="/export" />
</virtual-server-class>
...
```

Variables in subelements override variables in the parent elements. For example, it is possible to set a variable for a class of virtual servers and override it with a definition of the same variable in an individual virtual server.

## Sample server.xml File

When you first install the Windows version of Sun ONE Application Server, the `server.xml` file looks like this:

```

<?xml version="1.0" encoding="UTF-8"?>
<!-- server_7_0_dtd version: 1.1.2.39 -->
<!DOCTYPE server PUBLIC "-//Sun Microsystems Inc.//DTD Sun ONE Application Server
7.0//EN" "file:///C:/Sun/AppServer7/lib/dtds/sun-server_1_0.dtd">
<server name="server1" log-root="C:/Sun/AppServer7/domains/domain1/server1/logs"
application-root="C:/Sun/AppServer7/domains/domain1/server1/applications"
session-store="C:/Sun/AppServer7/domains/domain1/server1/session-store">
    <http-service qos-enabled="false">
        <http-listener id="http-listener-1" address="0.0.0.0" port="1024"
acceptor-threads="1" blocking-enabled="false" security-enabled="false"
default-virtual-server="server1" server-name="goliath" enabled="true"/>
        <mime id="mime1" file="mime.types"/>
        <acl id="acl1"
file="C:/Sun/AppServer7/domains/domain1/server1/config/generated.server1.acl"/>
        <virtual-server-class id="defaultclass" config-file="obj.conf"
default-object="default" accept-language="false" enabled="true">
            <virtual-server id="server1" http-listeners="http-listener-1"
hosts="goliath" mime="mime1" state="on" accept-language="false">
                <auth-db id="default" database="default"/>
                <property name="dir" value=""/>
                <property name="nice" value=""/>
                <property name="user" value=""/>
                <property name="group" value=""/>
                <property name="chroot" value=""/>
                <property name="docroot"
value="C:/Sun/AppServer7/domains/domain1/server1/docroot"/>
                <property name="accesslog"
value="C:/Sun/AppServer7/domains/domain1/server1/logs/access"/>
            </virtual-server>
        </virtual-server-class>
    </http-service>
    <iiop-service>
        <orb message-fragment-size="1024" steady-thread-pool-size="10"
max-thread-pool-size="200" idle-thread-timeout-in-seconds="300"
max-connections="1024" monitoring-enabled="false"/>
    </iiop-service>

```

```

    <iiop-listener id="orb-listener-1" address="goliath" port="3700"
enabled="true">
    </iiop-listener>
</iiop-service>
<web-container monitoring-enabled="false" >
</web-container>
    <ejb-container steady-pool-size="32" pool-resize-quantity="16"
max-pool-size="64" cache-resize-quantity="32" max-cache-size="512"
pool-idle-timeout-in-seconds="600" cache-idle-timeout-in-seconds="600"
removal-timeout-in-seconds="5400" victim-selection-policy="nru" commit-option="B"
monitoring-enabled="false">
    </ejb-container>
    <mdb-container steady-pool-size="10" pool-resize-quantity="2"
max-pool-size="60" idle-timeout-in-seconds="600" monitoring-enabled="false">
    </mdb-container>
    <jms-service port="7676" admin-user-name="admin" admin-password="admin"
init-timeout-in-seconds="30" enabled="true">
    </jms-service>
    <log-service file="C:/Sun/AppServer7/domains/domain1/server1/logs/server.log"
level="INFO" log-stdout="true" log-stderr="true"
echo-log-messages-to-stderr="true" create-console="true"
log-virtual-server-id="false" use-system-logging="false">
    </log-service>
    <security-service default-realm="file" anonymous-role="ANYONE"
audit-enabled="false">
        <auth-realm name="file"
classname="com.ipplanet.ias.security.auth.realm.file.FileRealm">
            <property name="file"
value="C:/Sun/AppServer7/domains/domain1/server1/config/keyfile"/>
            <property name="jaas-context" value="fileRealm"/>
        </auth-realm>
        <auth-realm name="ldap"
classname="com.ipplanet.ias.security.auth.realm.ldap.LDAPRealm">
            <property name="directory" value="ldap://localhost:389"/>
            <property name="base-dn" value="o=isp"/>
            <property name="jaas-context" value="ldapRealm"/>

```

```

    </auth-realm>

    <auth-realm name="certificate"
classna me="com.iplanet.ias.security.auth.realm.certificate.CertificateRealm">
    </auth-realm>

    <!--

    <auth-realm name="solaris"
classna me="com.iplanet.ias.security.auth.realm.solaris.SolarisRealm">
        <property name="jaas-context" value="solarisRealm"/>
    </auth-realm>

    -->

</security-service>

    <transaction-service automatic-recovery="false" timeout-in-seconds="0"
tx-log-dir="C:/Sun/AppServer7/domains/domain1/server1/logs"
heuristic-decision="rollback" keypoint-interval="2048"
monitoring-enabled="false">

    </transaction-service>

    <java-config java-home="C:/Sun/AppServer7/jdk"
server-classpath="C:/Sun/AppServer7/lib/appserv-rt.jar;C:/Sun/AppServer7/jdk/lib/
tools.jar;C:/Sun/AppServer7/lib/appserv-ext.jar;C:/Sun/AppServer7/lib/appserv-cmp
.jar;C:/Sun/AppServer7/lib/appserv-ideplugin.jar;C:\Sun\AppServer7\imq\lib\imq.ja
r;C:\Sun\AppServer7\imq\lib\jaxm-api.jar;C:\Sun\AppServer7\imq\lib\imqadmin.jar;C
:\Sun\AppServer7\imq\lib\imqutil.jar;C:/Sun/AppServer7/lib/appserv-admin.jar;C:\S
un\AppServer7\share\lib\jaxrpc-impl.jar;C:\Sun\AppServer7\share\lib\jaxrpc-api.ja
r;C:\Sun\AppServer7\share\lib\jaxr-impl.jar;C:\Sun\AppServer7\share\lib\jaxr-api.
jar;C:\Sun\AppServer7\share\lib\jhall.jar;C:\Sun\AppServer7\share\lib\activation.
jar;C:\Sun\AppServer7\share\lib\mail.jar;C:\Sun\AppServer7\share\lib\saaj-api.jar
;C:\Sun\AppServer7\share\lib\saaj-impl.jar;C:\Sun\AppServer7\share\lib\commons-lo
gging.jar;C:\Sun\AppServer7\imq\lib\fscontext.jar;C:\Sun\AppServer7\imq\lib\provi
derutil.jar;C:/Sun/AppServer7/lib/appserv-jstl.jar"
classpath-suffix="C:/Sun/AppServer7/pointbase/client_tools/lib/pbclient42RE.jar"
env-classpath-ignored="true" debug-options="-Xdebug
-Xrunjdw p:transport=dt_socket,server=y,suspend=n" debug-enabled="false"
javac-options="-g">

        <jvm-options>-Dorg.xml.sax.parser=org.xml.sax.helpers.XMLReaderAdapter
</jvm-options>

        <jvm-options>-Dorg.xml.sax.driver=org.apache.crimson.parser.XMLReaderImpl
</jvm-options>

<jvm-options>-Djava.security.policy=C:/Sun/AppServer7/domains/domain1/server1/con
fig/server.policy</jvm-options>

```

Sample server.xml File

```
<jvm-options>-Djava.security.auth.login.config=C:/Sun/AppServer7/domains/domain1/
server1/config/login.conf</jvm-options>

<jvm-options>-Dcom.sun.jdo.api.persistence.model.multipleClassLoaders=reload
</jvm-options>

<jvm-options>-Djava.util.logging.manager=com.ipplanet.ias.server.logging.ServerLog
Manager</jvm-options>

<jvm-options>-Dcom.sun.aas.configRoot=C:/Sun/AppServer7\config</jvm-options>
    <jvm-options>-Dcom.sun.aas.imqLib=C:\Sun\AppServer7\imq\lib</jvm-options>
    <jvm-options>-Dcom.sun.aas.imqBin=C:\Sun\AppServer7\imq\bin</jvm-options>

<jvm-options>-Dcom.sun.aas.webServicesLib=C:\Sun\AppServer7\share\lib</jvm-option
s>
    <jvm-options>-Dsun.rmi.dgc.server.gcInterval=300000</jvm-options>
    <jvm-options> -Xrs -Xms128m -Xmx256m </jvm-options>
</java-config>
<resources>
</resources>
    <applications dynamic-reload-enabled="false"
dynamic-reload-poll-interval-in-seconds="2">
    </applications>
</server>
```

# Syntax and Use of `init.conf`

When the Sun ONE Application Server starts up, it looks in a file called `init.conf` in the `instance_dir/config` directory to establish a set of global variable settings that affect the server instance's behavior and configuration. Sun ONE Application Server executes all the directives defined in `init.conf`.

Except for the `Init` functions, the directives in `init.conf` specify a variable and a value, for example:

```
TempDir /tmp
```

The order of the directives is not important.

---

**NOTE** Directives noted with boolean values have the following equivalent values: `on/yes/true` and `off/no/false`.

---

---

**NOTE** When you edit the `init.conf` file, you must restart the server for the changes to take effect.

---

---

**NOTE** The `init.conf` interface is Unstable. An unstable interface may be experimental or transitional, and hence may change incompatibly, be removed, or be replaced by a more stable interface in the next release.

---

This chapter lists the global settings that can be specified in `init.conf` in Sun ONE Application Server 7.

The categories are:

- Init Functions
- Server Information
- DNS Lookup
- Threads, Processes and Connections
- Native Thread Pools
- CGI
- Error Logging
- ACL
- Security
- Chunked Encoding
- Miscellaneous

For an alphabetical list of directives, see Appendix C, “Alphabetical List of Directives in `init.conf`”.

---

**NOTE** Much of the functionality of the file cache is controlled by a configuration file called `nsfc.conf`. For information about `nsfc.conf`, see “`nsfc.conf`” on page 127 and the *Sun ONE Application Server Performance Tuning, Sizing, and Scaling Guide*.

---

## Init Functions

The `Init` functions load and initialize server modules and plugins, and they initialize log files. For more information about these functions, see the *Sun ONE Application Server Developer’s Guide to NSAPI*.

# Server Information

This sub-section lists the directives in `init.conf` that specify information about the server. They are:

- `NetSiteRoot`
- `TempDir`
- `TempDirSecurity`
- `User` (UNIX only)

## NetSiteRoot

Specifies the absolute pathname to the top-level directory under which the server's `bin` and `lib` directories can be found. There is no default value; the file must specify a value.

### Syntax

`NetSiteRoot path`

## TempDir

Specifies the directory on the local volume that the server uses for its temporary files. On UNIX, this directory must be owned by, and writable by, the user the server runs as. See also the directives `User` (UNIX only) and `TempDirSecurity`.

### Syntax

`TempDir path`

### Default

`/tmp` (UNIX)

`TEMP` (environment variable for Windows)

## TempDirSecurity

Determines whether the server checks if the `TempDir` directory is secure. On UNIX, specifying `TempDirSecurity off` allows the server to use `/tmp` as a temporary directory.

---

**CAUTION** Specifying `TempDirSecurity off` or using `/tmp` as a temporary directory on UNIX is highly discouraged. Using `/tmp` as a temporary directory opens a number of potential security risks.

---

**Syntax**

```
TempDirSecurity [on|off]
```

**Default**

```
on
```

## User (UNIX only)

The `User` directive specifies the UNIX user account for the server. If the server is started by the superuser or root user, the server binds to the `Port` you specify and then switches its user ID to the user account specified with the `User` directive. This directive is ignored if the server isn't started as `root`. The user account you specify should have *read* permission to the server's root and subdirectories. The user account should have write access to the `logs` directory and execute permissions to any CGI programs. The user account should not have write access to the configuration files. This ensures that in the unlikely event that someone compromises the server, they won't be able to change configuration files and gain broader access to your machine. Although you can use the `nobody` user, it isn't recommended.

**Syntax**

```
User name
```

*name* is the 8-character (or less) login name for the UNIX user account.

**Default**

If there is no `User` directive, the server runs with the user account it was started with.

**Examples**

```
User http
```

```
User server
```

```
User nobody
```

# DNS Lookup

This section lists the directives in `init.conf` that affect DNS lookup. The directives are:

- AsyncDNS
- DNS

## AsyncDNS

Specifies whether asynchronous DNS is used. The `DNS` directive must be set to `on` for this directive to take effect. The value is either `on` or `off`. If DNS is enabled, enabling asynchronous DNS improves server performance.

### Default

The default is `off`.

## DNS

The `DNS` directive specifies whether the server performs DNS lookups on clients that access the server. When a client connects to your server, the server knows the client's IP address but not its host name (for example, it knows the client as `198.95.251.30`, rather than its host name `www.a.com`). The server will resolve the client's IP address into a host name for operations like access control, CGI, error reporting, and access logging.

If your server responds to many requests per day, you might want (or need) to stop host name resolution; doing so can reduce the load on the DNS or NIS server.

### Syntax

```
DNS [on|off]
```

### Default

DNS host name resolution is `on` as a default.

### Example

```
DNS on
```

# Threads, Processes and Connections

In Sun ONE Application Server 7, acceptor threads on a listen socket accept connections and put them onto a connection queue. Session threads then pick up connections from the queue and service the requests. The session threads post more session threads if required at the end of the request. The policy for adding new threads is based on the connection queue state:

- Each time a new connection is returned, the number of connections waiting in the queue (the backlog of connections) is compared to the number of session threads already created. If it is greater than the number of threads, more threads are scheduled to be added the next time a request completes.
- The previous backlog is tracked, so that if it is seen to be increasing over time, and if the increase is greater than the `ThreadIncrement` value, and the number of session threads minus the backlog is less than the `ThreadIncrement` value, then another `ThreadIncrement` number of threads are scheduled to be added.
- The process of adding new session threads is strictly limited by the `RqThrottle` value.
- To avoid creating too many threads when the backlog increases suddenly (such as the startup of benchmark loads), the decision whether more threads are needed is made only once every 16 or 32 times a connection is made based on how many session threads already exist.

This subsection lists the directives in `init.conf` that affect the number and timeout of threads, processes, and connections. They are:

- `ConnQueueSize`
- `HeaderBufferSize`
- `IOTimeout`
- `KeepAliveThreads`
- `KeepAliveTimeout`
- `KernelThreads` (Windows only)
- `ListenQ`
- `MaxKeepAliveConnections`
- `PostThreadsEarly`
- `RcvBufSize`
- `RqThrottle`

- RqThrottleMin
- SndBufSize
- StackSize
- StrictHttpHeaders
- TerminateTimeout
- ThreadIncrement

Also see the section “Native Thread Pools” on page 107 for directives for controlling the pool of native threads.

## ConnQueueSize

Specifies the number of outstanding (yet to be serviced) connections that the application server can have. It is recommended that this value always be greater than the operating system limit for the maximum number of open file descriptors per process.

### Default

The default value is 5000.

## HeaderBufferSize

The size (in bytes) of the buffer used by each of the request processing threads for reading the request data from the client. The maximum number of request processing threads is controlled by the RqThrottle setting.

### Default

The default value is 8192 (8 KB).

## IOTimeout

Specifies the number of seconds the server waits for data to arrive from the client. If data does not arrive before the timeout expires then the connection is closed. By setting it to less than the default 30 seconds, you can free up threads sooner. However, you may also disconnect users with slower connections.

### Syntax

IOTimeout *seconds*

**Default**

30 seconds for servers that don't use hardware encryption devices and 300 seconds for those that do.

## **KeepAliveThreads**

This directive determines the number of threads in the keep-alive subsystem. It is recommended that this number be a small multiple of the number of processors on the system. (for example, a 2 CPU system should have 2 or 4 keep alive threads). The maximum number of keep-alive connections allowed (`MaxKeepAliveConnections`) should also be taken into consideration when choosing a value for this setting.

**Default**

1

## **KeepAliveTimeout**

This directive determines the maximum time that the server holds open an HTTP Keep-Alive connection or a persistent connection between the client and the server. The Keep-Alive feature for earlier versions of the server allows the client/server connection to stay open while the server processes the client request. The default connection is a persistent connection that remains open until the server closes it or the connection has been open for longer than the time allowed by `KeepAliveTimeout`.

The timeout countdown starts when the connection is handed over to the keep-alive subsystem. If there is no activity on the connection when the timeout expires, the connection is closed.

**Default**

The default value is 30 seconds. The maximum value is 300 seconds (5 minutes).

## **KernelThreads (Windows only)**

Sun ONE Application Server can support both kernel-level and user-level threads whenever the operating system supports kernel-level threads. Local threads are scheduled by NSPR within the process whereas kernel threads are scheduled by the host operating system. Usually, the standard debugger and compiler are intended for use with kernel-level threads. By setting `KernelThreads` to 1 (on), you ensure that the server uses only kernel-level threads, not user-level threads. By setting `KernelThreads` to 0 (off), you ensure that the server uses only user-level threads, which may improve performance.

**Default**

The default is 0 (off).

## ListenQ

Specifies the maximum number of pending connections on a listen socket. Connections that time out on a listen socket whose backlog queue is full will fail.

**Default**

The default value is platform-specific: 4096 (AIX), 200 (Windows), 128 (all others).

## MaxKeepAliveConnections

Specifies the maximum number of Keep-Alive and persistent connections that the server can have open simultaneously. Values range from 0 to 32768.

**Default**

256

## PostThreadsEarly

If this directive is set to 1 (on), the server checks the whether the minimum number of threads are available at a listen socket after accepting a connection but before sending the response to the request. Use this directive when the server will be handling requests that take a long time to handle, such as those that do long database connections.

**Default**

0 (off)

## RcvBufSize

Specifies the size (in bytes) of the receive buffer used by sockets. Allowed values are determined by the operating system.

**Default**

The default value is determined by the operating system. Typical defaults are 4096 (4K), 8192 (8K).

## RqThrottle

Specifies the maximum number of request processing threads that the server can handle simultaneously. Each request runs in its own thread.

There is additional discussion of this and other server configuration and performance tuning issues in the *Sun ONE Application Server Performance Tuning, Sizing, and Scaling Guide*.

**Default**

128

## **RqThrottleMin**

Specifies the number of request processing threads that are created when the server is started. As the load on the server increases, more request processing threads are created (up to a maximum of `RqThrottle` threads).

**Default**

48

## **SndBufSize**

Specifies the size (in bytes) of the send buffer used by sockets.

**Default**

The default value is determined by the operating system. Typical defaults are 4096 (4K), 8192 (8K).

## **StackSize**

Determines the maximum stack size for each request handling thread.

**Default**

The most favorable machine-specific stack size.

## **StrictHttpHeaders**

Controls strict HTTP header checking. If strict HTTP header checking is on, the server rejects connections that include inappropriately duplicated headers.

**Syntax**

`StrictHttpHeaders [on|off]`

**Default**

off

## TerminateTimeout

Specifies the time that the server waits for all existing connections to terminate before it shuts down.

### Default

30 seconds

## ThreadIncrement

The number of additional or new request processing threads created to handle an increase in the load on the server, for example when the number of pending connections (in the request processing queue) exceeds the number of idle request processing threads.

When a server starts up, it creates `RqThrottleMin` number of request processing threads. As the load increases, it creates `ThreadIncrement` additional request processing threads until `RqThrottle` request processing threads have been created.

### Default

The default value is 10.

# Native Thread Pools

This section lists the directives for controlling the size of the native thread pool. This thread pool consists entirely of native, OS-level threads. The native pool on UNIX is normally not engaged, as all threads are OS-level threads. Using native pools on UNIX may introduce a small performance overhead as they'll require an additional context switch; however, they can be used to localize the `stickyAttach` effect or for other purposes, such as resource control and management or to emulate single-threaded behavior for plug-ins.

You can specify `stickyAttach` as a property of the `java-config` element in the `server.xml` file as follows:

```
<java-config>
  ...
  <property name="stickyAttach" value="1" >
</java-config>
```

On Windows, the default native pool is always being used and Sun ONE Application Server uses fibers (user-scheduled threads) for initial request processing. Using custom additional pools on Windows introduces no additional overhead.

The directives are:

- `NativePoolStackSize`
- `NativePoolMaxThreads`
- `NativePoolMinThreads`
- `NativePoolQueueSize`

## **NativePoolStackSize**

Determines the stack size of each thread in the native thread pool.

### **Default**

0 (represents an operating-system-specific default value)

## **NativePoolMaxThreads**

Determines the maximum number of threads in the native thread pool.

### **Default**

128

## **NativePoolMinThreads**

Determines the minimum number of threads in the native thread pool.

### **Default**

1

## **NativePoolQueueSize**

Determines the number of threads that can wait in the queue for the thread pool. If all threads in the pool are busy, then the next request-handling thread that needs to use a thread in the native pool must wait in the queue. If the queue is full, the next request-handling thread that tries to get in the queue is rejected, with the result that it returns a busy response to the client. It is then free to handle another incoming request instead of being tied up waiting in the queue.

**Default**

0 (represents an unlimited queue size)

# CGI

This section lists the directives in `init.conf` that affect requests for CGI programs. The directives are:

- `CGIExpirationTimeout`
- `CGIStubIdleTimeout`
- `MaxCGIStubs`
- `MinCGIStubs`
- `WincgiTimeout` (Windows only)

## CGIExpirationTimeout

This directive specifies the maximum time in seconds that CGI processes are allowed to run before being killed.

The value of `CGIExpirationTimeout` should not be set too low - 300 seconds (5 minutes) would be a good value for most interactive CGIs; but if you have CGIs that are expected to take longer without misbehaving, then you should set it to the maximum duration you expect a CGI program to run normally. A value of 0 disables CGI expiration, which means that there is no time limit for CGI processes.

Note that on Windows platforms `init-cgi time-out` does not work, so you must use `CGIExpirationTimeout`.

**Default**

0 (unlimited)

## CGIStubIdleTimeout

This directive causes the server to kill any `CGIStub` processes that have been idle for the number of seconds set by this directive. Once the number of processes is at `MinCGIStubs`, the server does not kill any more processes.

**Default**

30

## MaxCGIStubs

Controls the maximum number of CGIStub processes the server can spawn. This is the maximum concurrent CGIStub processes in execution, not the maximum number of pending requests. The default value should be adequate for most systems. Setting this too high may actually reduce throughput.

### Default

10

## MinCGIStubs

Controls the number of processes that are started by default. The first CGIStub process is not started until a CGI program has been accessed. Note that if you have an `init-cgi` directive in the `init.conf` file, the minimum number of CGIStub processes are spawned at startup. The value must be less than the `MaxCGIStubs` value.

### Default

2

## WinCGITimeout (Windows only)

WinCGI processes that take longer than this value are terminated when this timeout (in seconds) expires.

### Default

60

# Error Logging

This section lists the directives in that affect error logging. They are:

- `ErrorLogDateFormat`
- `LogFlushInterval`
- `PidLog`

## ErrorLogDateFormat

The `ErrorLogDateFormat` directive specifies the date format that the server log uses.

**Syntax**

ErrorLogDateFormat *format*

The *format* can be any format listed in Appendix A, “Time Formats”.

**Default**

%d/%b/%Y:%H:%M:%S

**LogFlushInterval**

This directive determines the log flush interval, in seconds, of the log flush thread.

**Default**

30

**PidLog**

PidLog specifies a file in which to record the process ID (pid) of the base server process. Some of the server support programs assume that this log is in the server root, in `logs/pid`.

To shut down your server, kill the base server process listed in the pid log file by using a `-TERM` signal. To tell your server to reread its configuration files and reopen its log files, use `kill` with the `-HUP` signal.

If the `PidLog` file isn't writable by the user account that the server uses, the server does not log its process ID anywhere. The server won't start if it can't log the process ID.

**Syntax**

PidLog *file*

The *file* is the full path name and file name where the process ID is stored.

**Default**

There is no default.

**Examples**

```
PidLog /var/ns-server/logs/pid
```

```
PidLog /tmp/ns-server.pid
```

# ACL

This section lists the directives in `init.conf` relevant to access control lists (ACLs). They are:

- `ACLCacheLifetime`
- `ACLUserCacheSize`
- `ACLGroupCacheSize`

## **ACLCacheLifetime**

`ACLCacheLifetime` determines the number of seconds before cache entries expire. Each time an entry in the cache is referenced, its age is calculated and checked against `ACLCacheLifetime`. The entry is not used if its age is greater than or equal to the `ACLCacheLifetime`. If this value is set to 0, the cache is turned off.

If you use a large number for this value, you may need to restart the Sun ONE Application Server when you make changes to the LDAP entries. For example, if this value is set to 120 seconds, the Sun ONE Application Server might be out of sync with the LDAP server for as long as two minutes. If your LDAP is not likely to change often, use a large number.

### **Default**

120

## **ACLUserCacheSize**

`ACLUserCacheSize` determines the number of users in the User Cache.

### **Default**

200

## **ACLGroupCacheSize**

`ACLGroupCacheSize` determines how many group IDs can be cached for a single UID/cache entry.

### **Default**

4

# Security

This section lists the directives in `init.conf` that affect server access and security issues for Sun ONE Application Server. They are:

- Security
- SSLCacheEntries
- SSLClientAuthDataLimit
- SSLClientAuthTimeout
- SSLSessionTimeout
- SSL3SessionTimeout

## Security

The `Security` directive globally enables or disables SSL by making certificates available to the server instance. It must be `on` for virtual servers to use SSL. If set to `on`, the user is prompted for:

- The password to the trust database, which contains the server's private key(s)
- The PINs required by any installed cryptographic hardware

---

**NOTE** When you create a secure listen socket through the Administration interface, security is automatically turned on globally in `init.conf`. When you create a secure listen socket manually in `server.xml`, security must be turned on by editing `init.conf`.

---

For more information about enabling SSL for individual virtual servers, see Chapter 2, “Server Configuration Files”.

### Syntax

```
Security [on|off]
```

### Default

```
off
```

### Example

```
Security off
```

## SSLCacheEntries

Specifies the number of SSL sessions that can be cached. There is no upper limit.

### Syntax

`SSLCacheEntries` *number*

If the *number* is 0, the default value, which is 10000, is used.

## SSLClientAuthDataLimit

Specifies the maximum amount of application data, in bytes, that is buffered during the client certificate handshake phase.

### Default

The default value is 1048576 (1 MB).

## SSLClientAuthTimeout

Specifies the number of seconds after which the client certificate handshake phase times out.

### Default

60

## SSLSessionTimeout

The `SSLSessionTimeout` directive controls SSL2 session caching.

### Syntax

`SSLSessionTimeout` *seconds*

The *seconds* value is the number of seconds until a cached SSL2 session becomes invalid. If the `SSLSessionTimeout` directive is specified, the value of seconds is silently constrained to be between 5 and 100 seconds.

### Default

The default value is 100.

## SSL3SessionTimeout

The `SSL3SessionTimeout` directive controls SSL3 session caching.

### Syntax

`SSL3SessionTimeout` *seconds*

The *seconds* value is the number of seconds until a cached SSL3 session becomes invalid. The default value is 86400 (24 hours). If the `SSL3SessionTimeout` directive is specified, the value of seconds is silently constrained to be between 5 and 86400 seconds.

## Chunked Encoding

This section lists directives that control chunked encoding.

- `UseOutputStreamSize`
- `ChunkedRequestBufferSize`
- `ChunkedRequestTimeout`

These directives have equivalent Service SAF parameters in `obj.conf`. The `obj.conf` parameters override these directives. For more information, see the *Sun ONE Application Server NSAPI Developer's Guide*.

### UseOutputStreamSize

The `UseOutputStreamSize` directive determines the default output stream buffer size for the `net_read` and `netbuf_grab` NSAPI functions. For details about these functions, see the *Sun ONE Application Server NSAPI Developer's Guide*.

---

**NOTE** The `UseOutputStreamSize` parameter can be set to zero in the `obj.conf` file to disable output stream buffering. For the `init.conf` file, setting `UseOutputStreamSize` to zero has no effect.

---

#### Syntax

`UseOutputStreamSize` *size*

The *size* value is the number of bytes.

#### Default

The default value is 8192 (8 KB).

### ChunkedRequestBufferSize

The `ChunkedRequestBufferSize` directive determines the default buffer size for “un-chunking” request data.

**Syntax**

`ChunkedRequestBufferSize` *size*

The *size* value is the number of bytes.

**Default**

The default value is 8192.

## ChunkedRequestTimeout

The `ChunkedRequestTimeout` directive determines the default timeout for “un-chunking” request data.

**Syntax**

`ChunkedRequestTimeout` *seconds*

The *seconds* value is the number of seconds.

**Default**

The default value is 60 (1 minute).

## Miscellaneous

This section lists miscellaneous other directives in `init.conf`.

- `ChildRestartCallback`
- `HTTPVersion`
- `MaxRqHeaders`
- `ReentrantTimeFunctions` (Solaris only)
- `Umask` (UNIX only)

### ChildRestartCallback

This directive forces the callback of NSAPI functions that were registered using the `daemon_atrestart` NSAPI function when the server is restarting or shutting down. Values are `on`, `off`, `yes`, `no`, `true`, or `false`. For details about `daemon_atrestart`, see the *Sun ONE Application Server NSAPI Developer's Guide*.

**Default**

`no`

## HTTPVersion

The current HTTP version used by the server in the form *m.n*, where *m* is the major version number and *n* the minor version number.

### Default

The default value is 1.1.

## MaxRqHeaders

Specifies the maximum number of header lines in a request. Values range from 0 to 512.

### Default

64

## ReentrantTimeFunctions (Solaris only)

The `ReentrantTimeFunctions` directive specifies whether the server should use its own reentrant time formatting implementation instead of the implementation provided by the operating system. Using the server's reentrant implementation may provide a small performance improvement on computers with a very large number of CPUs.

The default value, `off`, instructs the server to use the operating system's implementation. This is the recommended value.

### Default

`off`

## Umask (UNIX only)

This directive specifies the umask value used by the NSAPI functions `system_fopenWA` and `system_fopenRW` to open files in different modes. Valid values for this directive are standard UNIX umask values.

For more information on these functions, see `system_fopenWA` and `system_fopenRW` in the *Sun ONE Application Server NSAPI Developer's Guide*.

Miscellaneous

# MIME Types

This appendix discusses the MIME types file. The sections are:

- Introduction
- Determining the MIME Type
- How the Type Affects the Response
- What Does the Client Do with the MIME Type?
- Syntax of the MIME Types File
- Sample MIME Types File

The `mime.types` file interacts with the `obj.conf` file. For more information about `obj.conf`, see the *Sun ONE Application Server Developer's Guide to NSAPI*.

---

**NOTE** The `mime.types` interface is Unstable. An unstable interface may be experimental or transitional, and hence may change incompatibly, be removed, or be replaced by a more stable interface in the next release.

---

## Introduction

The MIME types file in the `instance_dir/config` directory contains mappings between MIME (Multipurpose Internet Mail Extensions) types and file extensions. For example, the MIME types file maps the extensions `.html` and `.htm` to the type `text/html`:

```
type=text/html exts=htm,html
```

When the Sun ONE Application Server receives a web request for a resource from a client, it uses the MIME type mappings to determine what kind of resource is being requested.

MIME types are defined by three attributes: language (`lang`), encoding (`enc`), and content-type (`type`). At least one of these attributes must be present for each type. The most commonly used attribute is `type`. The server frequently considers the `type` when deciding how to generate the response to the client. (The `enc` and `lang` attributes are rarely used.)

The default MIME types file is called `mime.types`.

## Determining the MIME Type

During the `ObjectType` step in the request handling process, the server determines the MIME type attributes of the resource requested by the client. Several different functions can be used to determine the MIME type, but the most commonly used one is `type-by-extension`. This function tells the server to look up the MIME type according to the requested resource's file extension in the MIME types table.

The directive in `obj.conf` that tells the server to look up the MIME type according to the extension is:

```
ObjectType fn=type-by-extension
```

If the server uses a different function, such as `force-type`, to determine the `type`, then the MIME types table is not used for that particular request.

## How the Type Affects the Response

The server considers the value of the `type` attribute when deciding which `Service` directive in `obj.conf` to use to generate the response to the client.

By default, if the `type` does not start with `magnus-internal/`, the server just sends the requested file to the client. The directive in `obj.conf` that contains this instruction is:

```
Service method=(GET|HEAD|POST) type=~magnus-internal/* fn=send-file
```

By convention, all values of `type` that require the server to do something other than just send the requested resource to the client start with `magnus-internal/`.

For example, if the requested resource's file extension is `.map`, the type is mapped to `magnus-internal/imagemap`. If the extension is `.cgi`, `.exe`, or `.bat`, the type is set to `magnus-internal/cgi`:

```
type=magnus-internal/imagemap      exts=map
type=magnus-internal/cgi          exts=cgi,exe,bat
```

If the `type` starts with `magnus-internal/`, the server executes whichever `Service` directive in `obj.conf` matches the specified type. For example, if the type is `magnus-internal/imagemap`, the server uses the `imagemap` function to generate the response to the client, as indicated by the following directive:

```
Service method=(GET|HEAD) type=magnus-internal/imagemap fn=imagemap
```

## What Does the Client Do with the MIME Type?

The `Service` function generates the data and sends it to the client that made the request. When the server sends the data to the client, it also sends headers. These headers include whichever MIME type attributes are known (which is usually `type`).

When the client receives the data, it uses the MIME type to decide what to do with the data. For browser clients, the usual thing is to display the data in the browser window.

If the requested resource cannot be displayed in a browser but needs to be handled by another application, its `type` starts with `application/`, for example `application/octet-stream` (for `.bin` file extensions) or `application/x-maker` (for `.fm` file extensions). The client has its own set of user-editable mappings that tells it which application to use to handle which types of data.

For example, if the type is `application/x-maker`, the client usually handles it by opening Adobe FrameMaker to display the file.

## Syntax of the MIME Types File

The first line in the MIME types file identifies the file format and must read:

```
#--Sun Microsystems MIME Information
```

Other non-comment lines have the following format:

```
type=type/subtype exts=[file extensions]
```

- `type/subtype` is the type and subtype.
- `exts` are the file extensions associated with this type.

## Sample MIME Types File

Here is an example of a MIME types file:

```

#--Sun Microsystems MIME Information
# Do not delete the above line. It is used to identify the file type.
type=application/octet-stream      exts=bin,exe
type=application/oda                exts=oda
type=application/pdf                exts=pdf
type=application/postscript         exts=ai,eps,ps
type=application/rtf                exts=rtf
type=application/x-mif               exts=mif,fm
type=application/x-gtar              exts=gtar
type=application/x-shar              exts=shar
type=application/x-tar               exts=tar
type=application/mac-binhex40       exts=hqx

type=audio/basic                    exts=au,snd
type=audio/x-aiff                   exts=aif,aiff,aifc
type=audio/x-wav                    exts=wav

type=image/gif                      exts=gif
type=image/ief                      exts=ief
type=image/jpeg                     exts=jpeg,jpg,jpe
type=image/tiff                     exts=tiff,tif
type=image/x-rgb                    exts=rgb
type=image/x-xbitmap                 exts=xbm
type=image/x-xpixmap                 exts=xpm
type=image/x-xwindowdump            exts=xwd

type=text/html                      exts=htm,html
type=text/plain                     exts=txt
type=text/richtext                  exts=rtx
type=text/tab-separated-values      exts=tsv
type=text/x-setext                  exts=etx

type=video/mpeg                     exts=mpeg,mpg,mpe
type=video/quicktime                exts=qt,mov
type=video/x-msvideo                exts=avi

enc=x-gzip                           exts=gz
enc=x-compress                      exts=z
enc=x-uuencode                      exts=uu,uue

type=magnus-internal/imagemap       exts=map
type=magnus-internal/parsed-html    exts=shtml
type=magnus-internal/cgi             exts=cgi,exe,bat
type=magnus-internal/jsp             exts=jsp

```

# Other Configuration Files

This chapter summarizes the **Purpose, Location, and Contents** or **Syntax** of important configuration files not discussed in other chapters, then briefly describes all directives or parameters allowed in each file (if any) in a table. Cross references are listed after **See Also** headings when other chapters or manuals describe some of the directives or parameters in more detail. Configuration files that should never be modified are not listed in this chapter.

The following configuration files are described in alphabetical order:

- `dbswitch.conf`
- Deployment Descriptors
- `generated.instance.acl`
- `nsfc.conf`
- `password.conf`
- `server.policy`

## dbswitch.conf

### **Purpose**

Specifies the LDAP directory that Sun ONE Application Server uses.

---

### **NOTE**

The `dbswitch.conf` interface is Unstable. An unstable interface may be experimental or transitional, and hence may change incompatibly, be removed, or be replaced by a more stable interface in the next release.

---

**Location**`instance_dir/config`**Syntax**

```
directory name LDAP_URL
name: property1 [value1]
name: property2 [value2]
...
```

The default contents of this file are as follows:

```
directory default null:///none
```

Edit the file as follows for anonymous binding over SSL:

```
directory default ldaps://directory.sun.com:636:/dc%3Dcom
```

Edit the file as follows for anonymous binding *not* over SSL:

```
directory default ldap://directory.sun.com:389:/dc%3Dcom
```

**See Also**

“User Database Selection” on page 87

The following table describes properties in the `dbswitch.conf` file. The left column lists the property names. The second column from the left lists allowed values. The third column from the left lists default values. The right column lists property descriptions.

**Table 5-1** dbswitch.conf

Property	Allowed Values	Default Value	Description
<code>nsessions</code>	A positive integer	8	The number of LDAP connections for the database.
<code>dyngroups</code>	<code>off</code> , <code>on</code> , <code>recursive</code>	<code>on</code>	Determines how dynamic groups are handled. If <code>off</code> , dynamic groups are not supported. If <code>on</code> , dynamic groups are supported. If <code>recursive</code> , dynamic groups can contain other groups.
<code>binddn</code>	A valid DN		The DN used for connecting to the database. If both <code>binddn</code> and <code>bindpw</code> are not present, binding is anonymous.
<code>bindpw</code>			The password used for connecting to the database. If both <code>binddn</code> and <code>bindpw</code> are not present, binding is anonymous.

**Table 5-1** dbswitch.conf

Property	Allowed Values	Default Value	Description
dcsuffix	A valid DN (relative to the LDAP URL)	none	<p>If present, the default value of the base DN for the request's virtual server is determined by a DC tree lookup, starting at the <code>dcsuffix</code> DN, of the virtual server's <code>hosts</code> attribute that matches the client-supplied <code>Host</code> header. If no <code>hosts</code> attribute matches, the <code>server-name</code> attribute of the parent <code>http-listener</code> is used.</p> <p>If not present, the default value of the base DN is the <code>base DN</code> value in the LDAP URL.</p> <p>The <code>basedn</code> attribute of an <code>auth-db</code> element in the <code>server.xml</code> file overrides this value.</p>
digestauth	off, on	off	<p>Specifies whether the database can do digest authentication. If <code>on</code>, a special Directory Server plugin is required. For information about how to install this plugin, see the <i>Sun ONE Application Server Administrator's Guide</i>.</p>

If an LDAP database is schema compliant, the base DN of the access is computed using a DC tree lookup of the `virtual-server` element's `hosts` attribute that matches the client-supplied `Host` header. If no `hosts` attribute matches, the `server-name` attribute of the parent `http-listener` is used. The result must contain an `inetDomainBaseDN` attribute that contains the base DN. This base DN is taken as is and is not relative to any of the base DN values.

## Deployment Descriptors

### Purpose

Configures features specific to the Sun ONE Application Server for deployed modules and applications.

### Location

The `META-INF` or `WEB-INF` directory of a module or application.

**See Also**

The following table shows where to find more information about Sun ONE Application Server deployment descriptors. The left column lists the deployment descriptors, and the right column lists where to find more information about those descriptors.

**Table 5-2** Sun ONE Application Server Descriptors

Deployment Descriptor	Where to Find More Information
sun-application.xml	<i>Sun ONE Application Server Developer's Guide</i>
sun-web.xml	<i>Sun ONE Application Server Developer's Guide to Web Applications</i>
sun-ejb-jar.xml and sun-cmp-mapping.xml	<i>Sun ONE Application Server Developer's Guide to Enterprise JavaBeans Technology</i>
sun-application-client.xml and sun-acc.xml	<i>Sun ONE Application Server Developer's Guide to Clients</i>
sun-ra.xml	<i>Sun ONE J2EE CA Service Provider Implementation Administrator's Guide</i>

## generated.instance.acl

**Purpose**

Sets permissions for access to the server instance. This is the default ACL file; you can create and use others.

---

**NOTE** The ACL file interface is Unstable. An unstable interface may be experimental or transitional, and hence may change incompatibly, be removed, or be replaced by a more stable interface in the next release.

---

**Location**

*instance\_dir*/config

**See Also**

*Sun ONE Application Server Administrator's Guide to Security*

# nsfc.conf

## Purpose

Sets file cache parameters. This file is present only if file cache parameters have been changed from their defaults.

---

## NOTE

The `nsfc.conf` interface is Unstable. An unstable interface may be experimental or transitional, and hence may change incompatibly, be removed, or be replaced by a more stable interface in the next release.

---

## Location

`instance_dir/config`

## Syntax

`parameter=value`

## See Also

*Sun ONE Application Server Performance Tuning, Sizing, and Scaling Guide*

The following table describes parameters in the `nsfc.conf` file. The left column lists the parameter names. The second column from the left lists allowed values. The third column from the left lists default values. The right column lists parameter descriptions.

**Table 5-3** nsfc.conf

Parameter	Allowed Values	Default Value	Description
FileCacheEnable	on, off	on	Enables the file cache.
CacheFileContent	on, off	on	Enables caching of file contents as well as file information for files smaller than <code>MediumFileSizeLimit</code> (smaller than <code>SmallFileSizeLimit</code> if <code>TransmitFiles</code> is on).
MaxAge	Number of seconds	30	The maximum age of a valid cache entry. This setting controls how long cached information is used once a file has been cached. An entry older than <code>MaxAge</code> is replaced by a new entry for the same file.

**Table 5-3** nsfc.conf

Parameter	Allowed Values	Default Value	Description
MediumFileSizeLimit	Limited by available memory	537600 (525K)	(UNIX only) Maximum size of a file that can be cached as a memory-mapped file (if <code>TransmitFiles</code> is off).
MediumFileSpace	Limited by available memory	10485760 (10 M)	Total size of all files that are cached as memory-mapped files (if <code>TransmitFiles</code> is off).
SmallFileSizeLimit	Limited by available memory	2048 (2K)	(UNIX only) Maximum size of a file that can be read into memory.
SmallFileSpace	Limited by available memory	1048576 (UNIX, 1 M), 0 (Windows)	Total size of all files that are read into memory.
TransmitFiles	on, off	on (Windows), off (UNIX)	Enables use of the <code>TransmitFile</code> system call. Not supported on IRIX, Compaq, or Linux.
MaxFiles		1024	Maximum number of files in the file cache.
HashInitSize	Limited by available memory	0	Initial number of hash buckets. If 0, the number of hash buckets is dynamically determined as $2 * \text{MaxFiles} + 1$ .
CopyFiles	on, off	on	(Windows only) Prevents sharing violations by copying files to a temporary directory.
TempDir	A path	<i>system_temp/instance</i>	Specifies a temporary directory for the file cache if <code>CopyFiles</code> is on.

## password.conf

### Purpose

By default, the application server prompts the administrator for the SSL key database password before starting up. If you want the application server to be able to restart unattended, you need to save the password in a `password.conf` file. Be sure that your system is adequately protected so that this file and the key databases are not compromised.

### Location

*instance\_dir/config*

This file is not present by default. You must create it if you need it.

### Syntax

*PKCS#11\_module\_name:password*

If you are using the internal PKCS#11 software encryption module that comes with the server, type the following:

*internal:password*

If you are using a different PKCS#11 module, for example for hardware encryption or hardware accelerators, you will need to specify the name of the PKCS#11 module, followed by the password, for example:

*internal:password*

### See Also

*Sun ONE Application Server Administrator's Guide*

## server.policy

### Purpose

Controls what access applications have to resources. This is the standard J2SE policy file.

### Location

*instance\_dir/config*

### Syntax

```
grant [codeBase "path"] {
    permission permission_class "package", "permission_type";
    ...
};
```

### See Also

*Sun ONE Application Server Developer's Guide*

<http://java.sun.com/docs/books/tutorial/security1.2/tour2/index.html>

server.policy

# Time Formats

This appendix describes the format strings used for dates and times in the server log. You use these formats in the `ErrorLogDateFormat` directive in `init.conf`.

The following table describes the format strings for dates and times. The left column lists time format symbols, and the right column explains the meanings of the symbols.

**Table A-1** Time formats

Symbol	Meaning
%a	Abbreviated weekday name (3 chars)
%d	Day of month as decimal number (01-31)
%S	Second as decimal number (00-59)
%M	Minute as decimal number (00-59)
%H	Hour in 24-hour format (00-23)
%Y	Year with century, as decimal number, up to 2099
%b	Abbreviated month name (3 chars)
%h	Abbreviated month name (3 chars)
%T	Time "HH:MM:SS"
%X	Time "HH:MM:SS"
%A	Full weekday name
%B	Full month name
%C	"%a %b %e %H:%M:%S %Y"
%c	Date & time "%m/%d/%y %H:%M:%S"
%D	Date "%m/%d/%y"

**Table A-1** Time formats

<b>Symbol</b>	<b>Meaning</b>
%e	Day of month as decimal number (1-31) without leading zeros
%I	Hour in 12-hour format (01-12)
%j	Day of year as decimal number (001-366)
%k	Hour in 24-hour format (0-23) without leading zeros
%l	Hour in 12-hour format (1-12) without leading zeros
%m	Month as decimal number (01-12)
%n	line feed
%p	A.M./P.M. indicator for 12-hour clock
%R	Time "%H:%M"
%r	Time "%I:%M:%S %p"
%t	tab
%U	Week of year as decimal number, with Sunday as first day of week (00-51)
%w	Weekday as decimal number (0-6; Sunday is 0)
%W	Week of year as decimal number, with Monday as first day of week (00-51)
%x	Date "%m/%d/%Y"
%y	Year without century, as decimal number (00-99)
%%	Percent sign

# Alphabetical List of Server Configuration Elements

## A

- acl 36
- admin-service 30
- applications 81
- auth-db 43
- auth-realm 60

## C

- connector-module 86
- custom-resource 70

## D

- description 29

## E

- ejb-container 49
- ejb-module 84

## H

external-jndi-resource 71

## H

http-listener 32

http-qos 43

http-service 30

## I

iiop-listener 47

iiop-service 44

## J

j2ee-application 83

java-config 65

jdbc-connection-pool 77

jdbc-resource 72

jms-resource 74

jms-service 55

jvm-options 68

## L

lifecycle-module 82

log-service 57

**M**

mail-resource 72  
mdb-container 53  
mime 35

**O**

orb 45

**P**

persistence-manager-factory-resource 76  
profiler 67  
property 28

**R**

resources 69

**S**

security-service 59  
server 27  
server-instance 30  
ssl 34  
ssl-client-config 46

**T**

**T**

transaction-service 62

**V**

virtual-server 38

virtual-server-class 37

**W**

web-container 48

web-module 85

# Alphabetical List of Directives in init.conf

## A

ACLCacheLifetime 112  
ACLGroupCacheSize 112  
ACLUserCacheSize 112  
AsyncDNS 101

## C

CGIExpirationTimeout 109  
CGIStubIdleTimeout 109  
ChildRestartCallback 116  
ChunkedRequestBufferSize 115  
ChunkedRequestTimeout 116  
ConnQueueSize 103

## D

DNS 101

E

## E

ErrorLogDateFormat 110

## H

HeaderBufferSize 103

HTTPVersion 117

## I

IOTimeout 103

## K

KeepAliveThreads 104

KeepAliveTimeout 104

KernelThreads (Windows only) 104

## L

ListenQ 105

LogFlushInterval 111

## M

MaxCGIStubs 110

MaxKeepAliveConnections 105

MaxRqHeaders 117

MinCGIStubs 110

**N**

NativePoolMaxThreads 108

NativePoolMinThreads 108

NativePoolQueueSize 108

NativePoolStackSize 108

NetSiteRoot 99

**P**

PidLog 111

PostThreadsEarly 105

**R**

RcvBufSize 105

ReentrantTimeFunctions (Solaris only) 117

RqThrottle 105

RqThrottleMin 106

**S**

Security 113

SndBufSize 106

SSL3SessionTimeout 114

SSLCacheEntries 114

SSLClientAuthDataLimit 114

SSLClientAuthTimeout 114

SSLSessionTimeout 114

StackSize 106

## T

StrictHttpHeaders 106

## T

TempDir 99

TempDirSecurity 99

TerminateTimeout 107

ThreadIncrement 107

## U

Umask (UNIX only) 117

UseOutputStreamSize 115

User (UNIX only) 100

## W

WincgiTimeout (Windows only) 110

# Index

## A

- accept-language attribute 38, 42
- acceptor-threads attribute 33
- Access Control List *see* ACL
- access log file 57
- accesslog variable 91
- acl element 36
- ACL file 36, 87
  - default 126
  - init.conf directives for 112
- ACL files 112
- ACLCacheLifetime init.conf directive 112
- ACLGroupCacheSize init.conf directive 112
- acls attribute 41
- ACLUserCacheSize init.conf directive 112
- address attribute 32, 47
- admin-password attribute 55
- admin-service element 29
- admin-user-name attribute 55
- alphabetical reference
  - init.conf directives 137
  - server.xml elements 133
- anonymous-role attribute 60
- append-version property 57
- application-root attribute 28
- applications
  - configuration of 83
  - location 28
- applications element 81
- assign-groups property 62

- AsyncDNS init.conf directive 101
- attributes, about 25
- audit-enabled attribute 60
- auth-db element 43
- auth-realm element 60
- automatic-recovery attribute 63

## B

- bandwidth-limit attribute 43
- basedn attribute 44
- base-dn property 62
- binddn property 124
- bindpw property 124
- blocking-enabled attribute 33
- bytecode-preprocessors attribute 67

## C

- cache 127
- CacheFileContent parameter 127
- cache-idle-timeout-in-seconds attribute 51
- cache-resize-quantity attribute 51
- certificates 62
  - settings in init.conf 113
- certmaps attribute 44
- cert-nickname attribute 34

CGI  
 settings in `init.conf` 109  
 variables for 91

CGIExpirationTimeout `init.conf` directive 109

CGIStubIdleTimeout `init.conf` directive 109

ChildRestartCallback `init.conf` directive 116

chroot variable 92

chunked encoding 115

ChunkedRequestBufferSize `init.conf` directive 115

ChunkedRequestTimeout `init.conf` directive 116

class-name attribute 83

classname attribute 61

classpath attribute 68, 83

classpath-prefix attribute 66

classpath-suffix attribute 66

client-auth-enabled attribute 35

CMP 76

cmt-max-runtime-exceptions property 54

commit-option attribute 52

config directory, location 17

config-file attribute 38, 40

configuration files 17  
 manually editing 20

configuration, dynamic 19

connection-limit attribute 43

connections, settings in `init.conf` 102

connection-validation-method attribute 79

connector-module element 86

ConnQueueSize `init.conf` directive 103

console, Windows 58

container-managed persistence 76

context-root attribute 86

convergence tree  
 auxiliary class `inetSubscriber` 89  
 in LDAP schema 88  
 organization of 89  
 user entries are called `inetOrgPerson` 89

CopyFiles parameter 128

create-console attribute 58

custom-resource element 70

## D

database attribute 44

database selection 43, 87

databaseName property 80

datasource-classname attribute 78

datasourceName property 81

dbswitch.conf file 87, 88, 123

dcsuffix property 125

debug attribute 73

debug-enabled attribute 65

debug-options attribute 65

default virtual server  
 for an `http-listener` element 33  
 for the entire server 38

default-object attribute 38, 41

default-principal attribute 59

default-principal-password attribute 60

default-realm attribute 59

default-virtual-server attribute 33

default-web-module attribute 40

deployment descriptors 125

description element 29

description property 81

digestauth property 125

dir variable 92

directory property 62

disable-distributed-transaction-logging property 64

DNS `init.conf` directive 101

docroot variable 91

domain component tree (dc) 89

Domain Name Service *see* DNS

dynamic reconfiguration 19

dynamic-reload-enabled attribute 82

dynamic-reload-poll-interval-in-seconds  
 attribute 82

dyngroups property 124

## E

echo-log-messages-to-stderr attribute 58

- ejb-container element 49
- ejb-module element 84
- enc parameter 120
- encoding, chunked 115
- enforce-bandwidth-limit attribute 43
- enforce-connection-limit attribute 43
- env-classpath-ignored attribute 67
- ErrorLogDateFormat init.conf directive 110
- external-jndi-resource element 71

## F

- factory-class attribute 70, 71, 77
- fail-all-connections attribute 80
- family attribute 33
- file attribute 58
  - for acl element 37
  - for mime element 36
- file cache 127
- file name extensions, MIME types 119
- file property 62
- FileCacheEnable parameter 127
- files, mapping types of 119
- formats, time 131
- from attribute 73

## G

- group variable 91
- group-base-dn property 62
- group-search-filter property 62
- group-target property 62

## H

- HashInitSize parameter 128
- HeaderBufferSize init.conf directive 103

- heuristic-decision attribute 63
- host attribute 73
- hosts attribute 41
  - checking against subject pattern 39
- HTTP listen socket 32
- HTTP requests, processing 18
- http-listener element 32
- http-listeners attribute 40
- http-qos element 43
- http-service element 30
- HTTPVersion init.conf directive 117
- HUP signal
  - PidLog and 111

## I

- id attribute
  - for acl element 37
  - for auth-db element 44
  - for http-listener element 32, 47
  - for mime element 36
  - for virtual-server element 40
  - for virtual-server-class element 37
- id variable 91
- idle-thread-timeout-in-seconds attribute 46
- idle-timeout-in-seconds attribute 53, 79
- IIOP listen socket 47
- iiop-listener element 47
  - definition in sun-server\_1\_0.dtd file 24
- iiop-service element 44
- imqBrokerHostName property 75
- imqBrokerHostPort property 75
- imqConfiguredClientID property 76
- imqDestinationName property 75
- inetOrgPerson in convergence tree 89
- Init functions 98
- init.conf file 18, 97
  - alphabetical list of directives 137
- initialization settings 18, 97
- init-timeout-in-seconds attribute 56
- instance-name property 56

instance-name-suffix property 56  
 IOTimeout init.conf directive 103  
 is-connection-validation-required attribute 79  
 is-failure-fatal attribute 83  
 is-isolation-level-guaranteed attribute 79

## J

j2ee-application element 83  
 J2SE policy file 129  
 JAAS 61  
 jaas-context property 61  
 Java Authentication and Authorization Service *see* JAAS  
 Java Database Connectivity *see* JDBC  
 Java Message Service *see* JMS  
 Java Naming and Directory Interface *see* JNDI  
 Java Platform Debugger Architecture *see* JPDA  
 Java Transaction Service *see* JTS  
 Java Virtual Machine *see* JVM  
 java-config element 65  
 javac-options attribute 66  
 java-home attribute 65  
 JavaMail 72  
 JDBC connection pool 77  
 JDBC resource 72  
 jdbc-connection-pool element 77  
 jdbc-resource element 72  
 jdbc-resource-jndi-name attribute 77  
 JMS 55, 74  
 jms-resource element 74  
 jms-service element 55  
 JNDI 71  
 jndi-lookup-name attribute 71  
 jndi-name attribute  
   for custom-resource element 70  
   for external-jndi-resource element 71  
   for jdbc-resource element 72  
   for jms-resource element 75  
   for mail-resource element 73

  for persistence-manager-factory-resource  
   element 77  
 JPDA debugging options 65  
 JTS 62  
 JVM 65  
   adding options to the server 68  
 jvm-options element 68

## K

KeepAliveThreads init.conf directive 104  
 KeepAliveTimeout init.conf directive 104  
 KernelThreads init.conf directive 104  
 keypoint-interval attribute 63

## L

lang parameter 120  
 LDAP 62, 87, 123  
   specifying which certificate mapping to use 44  
   Sun ONE schema 88  
 level attribute 58  
 lifecycle-module element 82  
 Lightweight Directory Access Protocol *see* LDAP  
 listen socket 32, 47  
 ListenQ init.conf directive 105  
 load-order attribute 83  
 locale attribute 28  
 location attribute 84, 85, 86, 87  
 log-file attribute 42  
 LogFlushInterval init.conf directive 111  
 logging  
   settings in init.conf 110  
   settings in server.xml 57  
 log-level attribute 58  
 log-root attribute 28  
 log-service element 57  
 log-stderr attribute 58  
 log-stdout attribute 58

log-virtual-server-id attribute 58

## M

mail-resource element 72  
 MaxAge parameter 127  
 max-cache-size attribute 51  
 MaxCGIStubs init.conf directive 110  
 max-connections attribute 46  
 MaxFiles parameter 128  
 MaxKeepAliveConnections init.conf directive 105  
 max-pool-size attribute 50, 53, 78  
 MaxRqHeaders init.conf directive 117  
 max-thread-pool-size attribute 46  
 max-wait-time-in-millis attribute 78  
 mdb-container element 53  
 MediumFileSizeLimit parameter 128  
 MediumFileSpace parameter 128  
 message-driven beans 53  
 message-fragment-size attribute 45  
 mime attribute 41  
 mime element 35  
 MIME types 119  
 mime.types file  
   default 120  
   overview of 19  
   sample of 122  
   server.xml element referencing 36  
   syntax 121  
 MinCGIStubs init.conf directive 110  
 monitoring-enabled attribute 46, 48, 52, 54, 64

## N

name attribute  
   for auth-realm element 61  
   for connector-module element 87  
   for ejb-module element 85  
   for j2ee-application element 84  
   for jdbc-connection-pool element 78

  for lifecycle-module element 83  
   for profiler element 68  
   for property element 29  
   for server element 28  
   for web-module element 85  
 native library path, configuring 66  
 native thread pools, settings in init.conf 107  
 native-library-path attribute 68  
 native-library-path-prefix attribute 66  
 native-library-path-suffix attribute 66  
 NativePoolMaxThreads init.conf directive 108  
 NativePoolMinThreads init.conf directive 108  
 NativePoolQueueSize init.conf directive 108  
 NativePoolStackSize init.conf directive 108  
 NetSiteRoot init.conf directive 99  
 networkProtocol property 81  
 nice variable 92  
 nsessions property 124  
 nsfc.conf file 127

## O

obj.conf file 18, 40  
   and virtual servers 18  
 oracle-xa-recovery-workaround property 64  
 orb element 45

## P

password  
   SSL key database 128  
 password property 80  
 password.conf file 128  
 persistence-manager-factory-resource element 76  
 PidLog init.conf directive 111  
 policy file 129  
 pool-idle-timeout-in-seconds attribute 51  
 pool-name attribute 72  
 pool-resize-quantity attribute 50, 53, 78

port attribute 32, 47, 55  
 port property 80  
 PostThreadsEarly init.conf directive 105  
 processes, settings in init.conf 102  
 profiler element 67  
 properties, about 28  
 property element 28

## Q

quality of service 43

## R

RcvBufSize init.conf directive 105  
 realm configuration 60  
 reconnect-delay-in-seconds property 54  
 reconnect-enabled property 54  
 reconnect-max-retries property 54  
 ReentrantTimeFunctions init.conf directive 117  
 removal-timeout-in-seconds attribute 52  
 request-handling process 19  
 request-response process 19  
 requirement rules 24  
 resource adapters 86  
 resources element 69  
 res-type attribute 70, 71, 75, 78  
 rmic-options attribute 66  
 roleName property 81  
 RqThrottle init.conf directive 105  
 RqThrottleMin init.conf directive 106

## S

search-bind-dn property 62  
 search-bind-password property 62  
 search-filter property 62

Secure Socket Layer *see* SSL  
 security 59  
   of listen sockets 32, 47  
   realm configuration 60  
   settings in init.conf 113  
 Security init.conf directive 113  
 security-enabled attribute 33  
 security-service element 59  
 send-cgi function, variables for 91  
 server  
   basic operation 17  
   HUP signal 111  
   init.conf directives that configure 99  
   initialization directives in init.conf 97  
   killing process of 111  
   modifying 17  
   TERM signal 111  
 server element 27  
 server log file 57  
   location 28, 58  
 server.policy file 129  
 server.xml file 18  
   elements in 26  
     alphabetical list 133  
   example of 92  
   location 23  
 server-classpath attribute 66  
 server-instance element 30  
 server-name attribute 33  
 serverName property 80  
 session-store attribute 28  
 single sign-on 42  
 SmallFileSizeLimit parameter 128  
 SmallFileSpace parameter 128  
 SndBufSize init.conf directive 106  
 SSL  
   configuring 34  
   settings in init.conf 113  
 ssl element 34  
 SSL key database password 128  
 ssl2-ciphers attribute 34  
 ssl2-enabled attribute 34  
 SSL3 client authentication 35  
 ssl3-enabled attribute 35

SSL3SessionTimeout init.conf directive 114  
 ssl3-tls-ciphers attribute 35  
 SSLCacheEntries init.conf directive 114  
 SSLClientAuthDataLimit init.conf directive 114  
 SSLClientAuthTimeout init.conf directive 114  
 ssl-client-config element 46  
 SSLSessionTimeout init.conf directive 114  
 sso-enabled property 42  
 sso-max-inactive-seconds property 42  
 sso-reap-interval-seconds property 42  
 StackSize init.conf directive 106  
 start-args attribute 56  
 state attribute 41  
 stderr output 58  
 stdout output 58  
 steady-pool-size attribute 50, 53, 78  
 steady-thread-pool-size attribute 46  
 store-protocol attribute 73  
 store-protocol-class attribute 73  
 StrictHttpHeaders init.conf directive 106  
 subelements, about 24  
 Sun customer support 15  
 Sun ONE Application Server *see* server  
 Sun ONE Message Queue 56  
 sun-acc.xml file 126  
 sun-application.xml file 126  
 sun-application-client.xml file 126  
 sun-cmp-mapping.xml file 126  
 sun-ejb-jar.xml file 126  
 sun-ra.xml file 126  
 sun-server\_1\_0.dtd file 24  
 sun-web.xml file 126  
 sybase-xa-recovery-workaround property 64

## T

TempDir init.conf directive 99  
 TempDir parameter 128  
 TempDirSecurity init.conf directive 99  
 TERM signal 111

TerminateTimeout init.conf directive 107  
 thread pools, settings in init.conf 107  
 ThreadIncrement init.conf directive 107  
 threads, settings in init.conf 102  
 time formats 131  
 timeout-in-seconds attribute 63  
 tls-enabled attribute 35  
 tls-rollback-enabled attribute 35  
 transaction log file 57, 63  
 transaction-isolation-level attribute 79  
 transaction-service element 62  
 TransmitFiles parameter 128  
 transport-protocol attribute 73  
 transport-protocol-class attribute 73  
 tx-log-dir attribute 63  
 type parameter 120  
 type-by-extension function 120

## U

Umask init.conf directive 117  
 UNIX user account, specifying 100  
 url property 81  
 UseOutputStreamSize init.conf directive 115  
 user attribute 73  
 user database selection 43, 87  
 User init.conf directive 100  
 user property 80  
 user variable 91  
 use-system-logging attribute 59

## V

validation-table-name attribute 80  
 value attribute 29  
 variables 90
 

- evaluation 92
- format of 90
- referencing in obj.conf 90

## Section **W**

- substitution, where allowed 90
- used in the interfaces 91
- victim-selection-policy attribute 52
- virtual servers
  - and the obj.conf file 18
  - log file for 57
- virtual-server element 38
- virtual-server-class element 37
- virtual-servers attribute 84, 86

## **W**

- web module, default 40
- web-container element 48
- web-module element 85
- WinCgiTimeout init.conf directive 110
- Windows console 58

## **X**

- xaresource-txn-timeout property 64